WORKSHARE PROFESSIONAL 9

INSTALLATION GUIDE







COMPANY INFORMATION

Workshare Professional Installation Guide

Workshare Ltd. (UK) 20 Fashion Street London E1 6PX UK Workshare Inc. (USA) 625 Market Street, 15th Floor San Francisco CA 94105 USA

Workshare Website: www.workshare.com

Trademarks

Trademarked names may appear throughout this guide. Instead of listing these here or inserting numerous trademark symbols, Workshare wishes to state categorically that no infringement of intellectual or other copyright is intended and that trademarks are used only for editorial purposes.

Disclaimers

The authors/publishers of this guide and any associated Help material have used their best efforts to ensure accuracy and effectiveness. Due to the continuing nature of software development, it may be necessary to distribute updated Help from time to time. The authors would like to assure users of their continued best efforts in supplying the most effective Help material possible.

The authors/publishers, however, make no warranty of any kind, expressed or implied, with regard to Workshare programs or Help material associated with them, including this guide. The authors/publishers shall not be liable in the event of incidental or consequential damages in connection with, or arising out of, the programs or associated Help instructions.

Copyright

© 2015. Workshare Ltd. All rights reserved. Workshare Professional and Workshare DeltaView are registered trademarks of Workshare Ltd. Workshare Compare, Workshare Protect, Workshare 3, Workshare DeltaServer, SafetyGain, and the Workshare logo are trademarks of Workshare Ltd. All other trademarks are those of their respective holders.



TABLE OF CONTENTS

Chapter 1.	Installation Overview	7
•	this Guide	
System Req	juirements	8
Certified	Environments	8
Installation	Guidelines	10
Workshare	Installation Files	11
Executab	iles	11
Update	e or Full Release?	12
Prerequis	site Components	12
Windows	s Installer Packages	13
Worksha	re PDF Publisher	13
Important I	nformation	14
Worksha	re Configuration Assistant	14
Re-Rur	nning the WCA	14
Worksha	re Microsoft Office Integration	15
Worksha	re OCR Functionality	15
Chapter 2.	Installation on Single Workstation	16
Installing W	/orkshare	17
Uninstalling	g Workshare	21
Chapter 3.	Licensing	22
Licensing W	/orkshare Professional	23
Standard In	stall	24
One-Time	e Log In	24
Deploymen	t with User Authenticated License	25
Create A	ccounts for Users	25
Compa	are and Protect	28
Deploymen	t with Enterprise License	29
Registry I	Location	29
End Hear	Interaction	20



WORKSHARE PROFESSIONAL INSTALLATION GUIDE

Capturing of Email	29
Renewing a License	30
Suppressing Expiry Reminders	31
Chapter 4. Configuration	32
Introducing the Workshare Configuration Manager	33
Administrator Mode and User Mode	33
Client Default Policy	34
Accessing the Workshare Configuration Manager	35
Searching Parameters	36
Setting Parameters	37
Recipient Checking	37
Deploying Configuration Settings	38
Saving Configuration Files	39
Loading Configuration Files	41
Upgrading to Workshare 9	42
Registry Configuration	42
Small Text Removal	42
Chapter 5. Integration	43
Introduction	44
Document Management Systems	44
Email Systems	45
Document Management Systems Integration	45
Autonomy iManage Integration – Configuring Server Integration	45
Adding File Types to the Autonomy iManage Server	45
Adding the Workshare Compare Application to the Autonomy iManage Server	46
Adding Workshare Professional as a Class to Autonomy iManage Server	47
Autonomy iManage Integration – Configuring Client Integration	48
Launching Applications within Autonomy iManage	49
Creating a Workshare Compare Icon on the Autonomy iManage Desktop	50
Autonomy iManage Integration - Configuring Workshare	50
Hummingbird Integration – DM5	52



WORKSHARE PROFESSIONAL INSTALLATION GUIDE

Adding Application and File Types to the Divis Server	54
Making Workshare Compatible with DM5	54
Making the Workshare Compare Icon Appear on the Desktop and Within a User Profile	55
Worldox Integration – Configuring Compare Files	55
NetDocuments Integration	57
SharePoint Integration - Server Installation	58
SharePoint Integration - Client Configuration	61
SharePoint Site Configuration	6
Email Systems Integration	62
Setting Up Microsoft Outlook	62
Setting Up IBM Lotus Notes	63
Resolving Email Addresses as Internal - Creating the Internal Domain List	63
Offline Mode	63
Issues with Custom Forms (Recipient Fields)	65
Chapter 6. Network Deployment	66
Overview	67
Installation File Summary	67
Deploying via the Command Line	68
Configuring Modules During Installation	68
Registry	69
DisableFeatures.ini	70
Installation Procedure with the Install Wizard	70
Deploying Workshare with the Executable	70
Installation Procedure using the MSI Files Directly	71
First Example Installation	7
Second Example Installation	72
Compulsory Properties – Professional/Compare/Protect	72
Optional Properties – Professional/Compare/Protect	73
Optional Properties – Desktop Client	75
Citrix Installation Guidelines	75
Enable Specific Users	76
Active Directory Deployment Guidelines	76



WORKSHARE PROFESSIONAL INSTALLATION GUIDE

	Assign	ed/Published to User Methods	76
	Deployin	g Workshare Professional/Compare/Protect	77
	Deployin	g Workshare Desktop	82
Арр	endix A.	Additional Msiexec.exe Parameters and Switches	86
M	ISIEXEC.E	KE Parameters and Switches	87
Арр	endix B.	Default Profile	91
W	orkshare	Default Profile	92
	Documer	nt Conversion Policy	92
	Hidden D	Pata Policy	92
	Hidden P	DF Data Policy	93
	Full Docu	ıment Restriction Policy	93
	External	Document Restriction Policy	93
	For Inter	nal Use Only Policy	94
	Confiden	tial Policy	94
	Highly Co	onfidential Policy	94
Арр	endix C.	Workshare Prerequisites	95
W	orkshare	Prerequisites	96
	Summary	/	96
	Microsof	t .NET Framework 4.5	96
	Microsof	t Visual C++ 2012 Redistributable Package (x86)	96
	Microsof	t Visual C++ 2012 Redistributable Package (x64)	96
	Microsof	t Visual Studio 2010 Tools for Office Runtime Setup	96



CHAPTER 1. INSTALLATION OVERVIEW

This chapter provides an overview of the installation of Workshare Professional, Workshare Compare and Workshare Protect as well as a list of system requirements. It includes the following sections:

- Introducing this Guide, page 8, explains what this installation guide covers.
- **System Requirements**, page 8, describes the system attributes required in order to install and run Workshare Professional/Compare/Protect.
- **Installation Guidelines**, page 10, describes the recommended installation and deployment procedure for Workshare Professional/Compare/Protect.
- Workshare Installation Files, page 11, describes the installation files and prerequisites for Workshare Professional/Compare/Protect.
- **Important Information**, page 14, provides important information that should be read before installing, configuring and deploying Workshare Professional/Compare/Protect.



INTRODUCING THIS GUIDE

This Installation Guide describes how to install, license and integrate Workshare products into your environment. It covers the installation of the following:

- Workshare Professional 9: Professional 9 helps you work on documents with other people. It is a
 suite of products that includes Compare, Protect and Connect. You can install the full suite or
 combinations of products, such as Compare and Connect or Protect and Compare.
- Workshare Protect 9: Protect 9 identifies and cleans metadata from documents, removing the
 risk of unintentional data leakage. When sending emails, users can remove hidden sensitive
 data, convert the documents to PDF or PDF/A and even replace attachments with a link to a
 Connect where others can review them. Additionally, Protect provides the ability to set policies
 to automatically clean attachments based on specific criteria.
- Workshare Compare 9: Compare 9 enables users to compare multiple documents to easily identify and review changes. Users can accept or reject changes and apply them from within Word or Workshare Compare. Documents can be compared from a DMS, CRM or Outlook.

Workshare Connect can be included in the Professional. Protect and Compare installations. Connect extends comparison and protection functionality with online services, for example, comparisons as well as Office documents can be securely saved and shared to Connect, and attachments can be replaced with a secure link to the document in Connect. Connect also includes a desktop sync app – an application that syncs content between Workshare Connect and your PC. At any time, you can access and review your Connect content as well as add files.

SYSTEM REQUIREMENTS

The system requirements for Workshare Professional/Compare/Protect 9 are as follows:

Minimum System Requirements	Intel Pentium 4 3.2GHz processor
	1.5GB RAM
	1GB free disk space
Recommended System Requirements	Intel Core 2 DUO @ 2.2GHz
	AMD Athlon 64 X2 4400+
	2GB RAM
	2GB free disk space

Certified Environments

Workshare Professional/Compare/Protect 9 have been tested and certified in a number of environments. If your environment is not included in the following list, it may still be a compatible environment. Contact Workshare Customer Support (support@workshare.com) for any help.

For details of which environments previous versions of Workshare Professional/Compare/Protect were certified against, refer to previous versions of release notes on the knowledge base.

INSTALLATION OVERVIEW

Note: Unless otherwise stated, all environments are the English version with the en-us language set.

Operating System:

- Microsoft Windows 10 (32 bit and 64 bit)
- Microsoft Windows 8.1 (32 bit and 64 bit) + Japanese
- Microsoft Windows 7 SP1 (32 bit and 64 bit) + Chinese Simplified & French

Citrix:

- With Microsoft Windows R2 Server 2012 (64 bit)
 - Citrix XenApp 7.5
 - Citrix XenDesktop 7.5
- With Microsoft Windows R2 Server 2008 SP1 (64 bit)
 - Citrix XenApp 6.5
 - Citrix XenDesktop 6.5
 - Citrix XenDesktop 5.6

Note: Check with your Citrix vendor about which Windows operating system supports your version of Citrix.

Microsoft Office System:

- Microsoft Office 2013 SP1 (32 bit) + Japanese
- Microsoft Office 2013 (32 bit) + Japanese
- Microsoft Office 2010 SP2 (32 bit) + Chinese Simplified & French
- Microsoft Office 2007 SP3 (32 bit)

Email System:

- Microsoft Outlook 2013 SP1 (32 bit) + Japanese
- Microsoft Outlook 2013 (32 bit) + Japanese
- Microsoft Outlook 2010 SP2 (32 bit) + Chinese Simplified & French
- Microsoft Outlook 2007 SP3 (32 bit)
- IBM Lotus Notes 9.0.1
- IBM Lotus Notes 9.0

Note: Interactive Protect and the replace email attachment with link feature of Workshare Protect is not supported in a Lotus Notes environment.

Microsoft SharePoint:

Microsoft SharePoint 2013 SP1

INSTALLATION OVERVIEW

DMS Integration:

Note: Check with your DMS vendor about which Windows operating system supports your DMS.

NetDocuments

Note: The NetDocuments integration requires that Microsoft Internet Explorer is installed (the NetDocuments login screen is displayed in an IE iframe) although it does not have to be the default browser.

Autonomy iManage:

- FileSite 9.2
- FileSite 9.0 Update 6
- FileSite 9.0 Update 5 (+ EMM)
- FileSite 8.5 SP3 Update 5/6
- DeskSite 9.2
- DeskSite 9.0 Update 6
- DeskSite 9.0 Update 5
- DeskSite 8.5 SP3 Update 5/6

• Open Text:

- eDOCS DM 10
- eDOCS DM 5.3.1 COM only (Patch 5)
- eDOCS DM 5.3 COM only (Patch 5 Rollup 4&5)

Worldox GX3

Note: Workshare recommends WBGX Version ID: 6EB.688.D48 (Mar 28 2014) 11.0 or later.

Workshare will endeavor to support future service packs of certified environments.

INSTALLATION GUIDELINES

This guide will take you through a typical Workshare installation. The general steps involved are as follows:

- 1. For DMS users, configure your DMS server and client (described in Chapter 5: Integration).
- 2. Install Workshare on a single workstation (described in *Chapter 2: Installation*).
- 3. Use the Workshare Configuration Manager (Administrator Mode) to configure Workshare as you want it to work in your organization (described in *Chapter 4: Configuration*).
- 4. Save the configuration to a deployment script (reg or adm file) (described in *Saving Configuration Files* in *Chapter 4: Configuration*).

INSTALLATION OVERVIEW

- 5. Deploy the configuration across your network using a deployment script so that Workshare will be configured uniformly across your organization.
- 6. Deploy Workshare across your network (described in Chapter 6: Network Deployment).

It is recommended that you follow the guidelines listed below when installing Workshare to ensure a smooth and trouble-free installation:

- Ensure that your system meets the recommended requirements for Workshare shown on page 7.
- Ensure that all important data is backed up prior to installation.
- Elevated/administrator privileges are required to install Workshare.
- Workshare MSI files should not be directly edited. Changes can be applied via a transform file (.mst) or other method of applying properties such as command line parameters.
- Transform files may be created via any third party software that supports Windows Installer technology.
- Workshare MSI files should not be repackaged. Certain custom actions that are contained in the original MSI file may be missed and may also prevent future upgrades.
- Workshare MSI files should not be patched with in-house authored MSP files as this may cause future upgrade issues and system instability.
- Additional customer specific files and Registry keys may be deployed alongside Workshare software as long as they do not interact or replace any files or Registry keys belonging to the product.
- No additional third party software should be bundled into any Workshare MSI.

If you have any queries about the installation of Workshare that are not dealt with in this guide, please contact Workshare Customer Support.

WORKSHARE INSTALLATION FILES

This section describes the Workshare executables, Windows Installer Packages and shared components.

Executables

A single, downloadable self-extracting executable will install Workshare Professional or Workshare Compare or Workshare Protect and (where necessary) the DMS integration. Workshare Professional/Compare/Protect can be installed to work with your local file system or with your DMS.

The installation executables are as follows:

Executable	Installs
Workshare.Professional.Bundle.exe	Workshare Professional (Compare, Protect and Connect)
Workshare.Compare.Bundle.exe	Workshare Compare (Compare and Connect)
Workshare.Protect.Bundle.exe	Workshare Protect (Protect and Connect)

INSTALLATION OVERVIEW

On a single workstation, the easiest way to install Workshare is to simply run the install executable file and answer any questions asked. Where a manual installation per computer is not feasible, you can deploy Workshare to multiple workstations using methods described in *Chapter 6: Network Deployment*.

Update or Full Release?

The Workshare installation files will depend on the type of release:

- Fast track fixes: Individual fast track fixes will be sent to individual customers via an MSP file.
- Fix rollups: An update which contains a roll up of all fast tracks created within the last 8-12 weeks will be sent to all customers via an MSP, EXE or MSI file.
- Full product releases: Full product releases will be via MSI and EXE files only.

Prerequisite Components

The prerequisites for Workshare Professional/Compare/Protect 9 depend on the version of the operating system and the version of Microsoft Office. They are described in the following table. Prerequisites for other versions of Workshare Professional/Compare/Protect may be slightly different.

Workshare 9 is a native x86 application. It normally requires the x86 prerequisites for proper operation. The exception is the Microsoft .NET Framework which must have the appropriate x86/x64 version installed.

Prerequisite	Version	os	Office	Notes
Microsoft .NET Framework 4.5	4.5.50709.17929	Windows 7, Server 2008, Server 2008 R2	NA	
Microsoft Visual C++ 2012 Redistributable Package (x86)	11.0.61030.0	All (including x64 versions)	NA	
Microsoft Visual C++ 2012 Redistributable Package (x64)	11.0.61030.0	x64 OS versions	NA	The right-click handler is written in x64 code and requires this prerequisite.
Microsoft Visual Studio 2010 Tools for Office Runtime Setup	10.0.40303.00	All	All	Visual Studio is NOT required.

Note: Microsoft .NET Framework should be installed first. The other prerequisite components can be installed in any order.

For further information about each prerequisite, refer to Appendix C: Workshare Prerequisites.



Windows Installer Packages

If you need to extract the MSI and prerequisites from the executables, you can do so using the /layout command. The *Downloading Files and Prereqs* dialog is displayed while the prerequisites and MSIs are downloaded to the same location as the executable. The 4 prerequisite executables are put in a folder called **redist**.

The following files are extracted from the executables:

Executable	Contents Extracted
Workshare.Professional.Bundle.exe	Workshare.Professional.msi WorkshareCompareForPowerPoint.msi
	Workshare.Desktop.msi
	Redist folder including the prerequisite executables (dotNetFx45_Full_x86_x64.exe, vcredist_x64.exe, vcredist_x86.exe, vstor_redist.exe)
Workshare.Compare.Bundle.exe	WorkshareCompare.msi
	WorkshareCompareForPowerPoint.msi
	Workshare.Desktop.msi
	Redist folder including the prerequisite executables (dotNetFx45_Full_x86_x64.exe, vcredist_x64.exe, vcredist_x86.exe, vstor_redist.exe)
Workshare.Protect.Bundle.exe	WorkshareProtect.msi
	Workshare.Desktop.msi
	Redist folder including the prerequisite executables (dotNetFx45_Full_x86_x64.exe, vcredist_x64.exe, vcredist_x86.exe, vstor_redist.exe)

If you install using an extracted MSI, you must first install all the prerequisite components described above.

Workshare PDF Publisher

When Workshare Professional/Compare/Protect is installed it creates a printer called **Workshare PDF Publisher** in the user's **Printers** folder. This is the printer that Workshare uses to convert documents to PDF.



IMPORTANT INFORMATION

Workshare Configuration Assistant

The Workshare Configuration Assistant (WCA) is a program that completes the installation process. The WCA is not optional as it performs actions that are required to correctly install the product. The install process automatically runs the WCA silently.

Re-Running the WCA

Following installation, the WCA can be run as a separate executable for any of the following reasons:

- To update an installation, such as to make Workshare compatible with a new DMS
- To install/uninstall specific Workshare features

When re-run, the WCA provides information on the progress of installation and any necessary messaging if any problems are encountered. If a problem is encountered, the user can access the online Workshare knowledge base which provides an extended description and, where possible, a solution to resolve the problem.

The executable is named **WMConfigAssistant.exe** and is found in the **Modules** folder of the installation directory. To be run, the WCA requires administration rights to the workstation.

The WCA executable can be run from the command line, from within a DOS window or using a batch (.bat) file. This should only be attempted by the network administrator or other qualified personnel. The WCA can be run silently, without any user interface and quietly, with a reduced user interface.

The WCA is also available from the Start Menu: Start > Programs > Workshare > Workshare Configuration Assistant.

To run the WCA from the command line, the following syntax should be used:

"C:\Program Files\Workshare\Modules\WMConfigAssistant.exe" /INSTALL /SILENT /LOGFILE="\\InstallMachine\Workshare\Uorkshare.log"

Where the switches can be:

Switch	Value
SILENT	Indicates that the WCA is to be run silently, with no user interface.
QUIET	Indicates that the WCA is to be run with a reduced user interface.



INSTALLATION OVERVIEW

Switch	Value	
LOGFILE	Name and location of the WCA log file. For example, LOGFILE="\\server\share\\logfile.log". The log file can either be stored at a shared location or stored locally on the workstation.	
	If a location is not specified for the log file it will be written to the local TEMP folder. By default the log file is named WorkshareConfig.log .	
	The WCA log file will provide details of all the steps the WCA has taken and can be passed to Workshare if any difficulties are encountered.	
	The log file is appended to, not overwritten, in order to retain all logged information. Therefore the latest details will be at the end of the log file.	
NOTESINIFILE_ PATH	Location of the notes.ini file. This should be specified in non-standard IBM Lotus Notes environments to ensure that Workshare components are added correctly to the INI file by the install.	

Note: The command must be entered on one line. You can use INSTALL, UNINSTALL, REINSTALL or REPAIR as the preceding switch. The use of " " should be used where there is character spacing in file paths.

Workshare Microsoft Office Integration

Workshare Professional/Compare/Protect can be installed with or without Microsoft Office integration. If you want to change the integration of Workshare Professional/Compare/Protect with Microsoft Office applications, go to the Control Panel, select the Workshare product and click Change. This will re-display the installation dialogs and you can change your integration settings.

By configuring Workshare Professional/Compare/Protect to run without a Microsoft Office integration, for example, by deselecting the Microsoft Word add-in, there will be no Workshare tab available in Microsoft Word. In this case, the comparison functionality is only available from the Workshare Compare application and the metadata removal functionality is only available when sending emails.

Workshare OCR Functionality

Workshare Compare includes OCR technology to enable comparison of PDFs that have been created directly from scanning. Where OCR has not been used and PDFs contain pure images of text, Workshare Compare applies OCR to the PDFs before performing comparisons.



CHAPTER 2. INSTALLATION ON SINGLE WORKSTATION

This chapter describes the procedure for installing Workshare Professional/Compare/Protect on a single workstation. It includes the following sections:

- **Installing Workshare**, page 17, describes the step-by-step procedure required to install Workshare Professional/Compare/Protect on a single workstation.
- **Uninstalling Workshare**, page 21, describes how to uninstall Workshare Professional/Compare/Protect.

The procedure for installing Workshare across a network is described in *Chapter 6: Network Deployment*.



INSTALLING WORKSHARE

The following procedure explains how to install Workshare Professional, Workshare Compare and Workshare Protect on a single workstation. Before beginning the installation procedure, make sure that all other programs are closed and disable any anti-virus software.

There is no need to uninstall previous versions of Professional. With an upgrade, any customized settings (public and user) are migrated whereas with a new install, the default settings are installed. If you are uninstalling and performing a new install and want to keep your settings, you should back up your configuration. Refer to *Upgrading to Workshare 9*.

During the installation of Workshare Professional, you can select which Workshare products to install (Compare, Protect and Connect) and during all installations, you can select what Office integrations you want. With a Workshare Professional, Compare and Protect installation, you can select which DMS integration(s) (if any) to install - Hummingbird, Autonomy iManage, Worldox, SharePoint or NetDocuments.


The installation executables are as follows:

Executable	Installs
Workshare.Professional.Bundle.exe	Workshare Professional (Compare, Protect and Connect)
Workshare.Compare.Bundle.exe	Workshare Compare (Compare and Connect)
Workshare.Protect.Bundle.exe	Workshare Protect (Protect and Connect)


INSTALLATION OVERVIEW

To install Workshare:

1. Double-click the install executable. The Workshare Installer is displayed.




- 2. If you want to select particular products or integrations, click "or choose products to install". If not, jump to step 6.
 - When installing Workshare Professional, the following is displayed:






When installing Workshare Compare, the following is displayed:



When installing Workshare Protect, the following is displayed:



3. Select from the following as available and as required:

Compare: Installs Compare enabling you to compare documents.

Protect: Installs Protect enabling you to clean metadata from documents.

Connect: Installs Connect enabling you to save and share files to Workshare Connect as well as synchronize between Connect and your desktop.



INSTALLATION OVERVIEW


Microsoft Outlook: Integrates the selected products within Microsoft Outlook.

Microsoft Word: Integrates the selected products within Microsoft Word.

Microsoft PowerPoint: Integrates the selected products within Microsoft PowerPoint.

Microsoft Excel: Integrates the selected products within Microsoft Excel.

4. Click Next. If you selected Compare or Protect, the following DMS Integration is displayed.



5. Select from the following as available and as required:

OpenText: Integrates the selected functionality within an OpenText DMS.

Microsoft SharePoint: Integrates the selected functionality within Microsoft SharePoint.

Autonomy iManage: Integrates the selected functionality within an Autonomy iManage DMS.


Worldox GX3: Integrates the selected functionality with Worldox.

NetDocuments: Integrates the comparison functionality with NetDocuments.

Note: Selecting a DMS here does not integrate Connect with the DMS. To integrate Connect with a DMS, download the relevant file from the **Services** tab of the Connect Admin Console.

INSTALLATION OVERVIEW

6. Click Install. Workshare creates the necessary folders and copy files. The installation process may take a few minutes. A progress bar indicates the progress of the installation.



7. After this process is completed, click **Finish**. This completes the installation of Workshare. For a full description of the Workshare functionality, refer to the relevant Workshare User Guide.

Note: Ensure that the system user has write access to the policy sets folder - ProgramData/Workshare/ PolicySets.

UNINSTALLING WORKSHARE

Workshare Professional/Compare/Protect should be uninstalled using the Control Panel. Uninstalling Workshare Professional/Compare/Protect will uninstall all the Workshare elements installed during the installation process.

Note: The uninstall process will not uninstall any prerequisites installed.



CHAPTER 3. LICENSING

This chapter describes the licensing procedure for Workshare. It includes the following sections:

- Licensing Workshare Professional, page 23, describes the process for licensing your Workshare product.
- Standard Install, page 24, describes how to license Workshare products when installing on individual machines.
- **Deployment with User Authenticated License**, page 25, describes how to license Workshare products with a User Authenticated license when rolling out to multiple users.
- **Deployment with Enterprise License**, page 29, describes how to license Workshare products with an Enterprise license when rolling out to multiple users.
- Renewing a License, page 30, describes how to renew a Workshare license.

Note: You do NOT need to uninstall or remove any existing lic file. Workshare Professional/Compare/ Protect 9 will ignore it.



LICENSING WORKSHARE PROFESSIONAL

The first step of any installation is to purchase your product. To do so:


- 1. Create a Workshare Connect account on my.workshare.com
- 2. Purchase your product
- 3. Download the installation file

A license is created and assigned to your account. In order to license your product, select the method most suited to your environment.

- **Standard Install**: When you are installing Workshare on individual machines, user authenticated licensing is recommended.
- **Deployment with User Authenticated License**: When your users will be using Connect functionality in Professional and you want an accurate view of license usage as well as the ability to track and manage users centrally, user authenticated licensing is recommended.
- **Deployment with Enterprise License**: When your users won't be using Connect functionality in Professional or you have restrictive firewall settings or you operate in a Citrix environment, enterprise licensing is recommended.

The steps in each method are outlined below:








STANDARD INSTALL

When you are installing Workshare on individual machines, user authenticated licensing is recommended. This is where users are required to have a Connect account and sign in to Connect on a one-off basis to retrieve their license entitlements.

One-Time Log In

After installation, the first time a user accesses Workshare functionality, for example, by clicking any option in the Workshare tab, they are prompted to log in to Workshare Connect in order to retrieve their license entitlements.



Note: They can also open the Workshare Configuration Manager, select the **My Products** tab and click **Sign in**.

They must enter their Workshare Connect credentials (email address and password) and click **Sign in**. The license entitlements for your account are retrieved and shown in the **My Products** tab of the Workshare Configuration Manager.

Users who do not yet have a Connect account can click **Create an account** in the login dialog. Workshare checks their email address and will automatically register them against your corporate Workshare Connect account and update their license entitlement.



DEPLOYMENT WITH USER AUTHENTICATED LICENSE

When your users will be using Connect functionality in Professional and you want an accurate view of license usage as well as the ability to track and manage users centrally, user authenticated licensing is recommended. After you have deployed the product, your users are required to have a Connect account and sign in to Connect on a one-off basis to retrieve their license entitlements. To simplify this process, you can create accounts for your users from the Workshare Connect Admin Console.

Create Accounts for Users

When you are deploying Workshare Professional across your network, you should first add your users to your Workshare Connect account. Users need a Connect account so that they can log into Connect on first use of Professional in order to validate their entitlement to Workshare products and receive their Professional license.

Adding users to your Connect account is a simple process performed on the Connect Admin Console and you may add them individually or up to 100 at one time using a CSV file. Users are people in your network using one of your Workshare Connect licenses and all users share the same domain name.

Note: Any user who is part of your domain will be assigned to your company account even if they sign up for a personal account.

Adding a user "invites" that user to your Workshare Connect account and they receive an email asking them to validate their account and create a password for it. Only when the invited user validates their account are they considered a licensed user on your account.

Tip! A video describing this process can be found at https://www.youtube.com/watch?v=x1lxAut6lsg&feature=youtu.be.


If you do not have access to the Admin Console, for example, you have only Compare installed with a personal Connect account, you can create accounts for your users following the procedure in *Compare and Protect*.

To add multiple users:

- 1. Create a CSV file containing the user account information (up to 100 users). Ensure the file has the following mandatory headers: "email address" and "first name". You may also include the following headers: "last name", "job title" and "phone number".
- 2. Go to my.workshare.com and log in to your account.
- 3. Click your user name in the Connect topbar and select Admin Console.
- 4. Select the User Management tab.



5. Click Add Bulk Users.




- 6. Click Choose File and browse to where you have saved your CSV file with all your user details.
- 7. Select the file and click **Open**.
- 8. In the *Add Bulk Users* window, click **Import**. The user details are added to your account and a registration email is sent to all the email address specified, inviting them to validate their Connect account.

Your users will appear in the **User Management** tab.



To add a single user:

1. In the User Management tab of the Admin Console, select **Add User**.



- 2. In the **E-mail** field, enter an email address for the user this must be from your registered email domain.
- 3. In the **First Name** field, enter a name for the user.

Note: The default role for a user is that of **User**. If you want to create an administrator user with access rights to the Admin Console, select **Account Admin** from the **Role** dropdown list.

- 4. Complete the other fields and add a picture for the user if required. The user will be able to edit these personal settings when they have validated their account. The user cannot change their registered email address.
- 5. Click **Add User**. A registration email is sent to the email address specified and the user is invited to validate their Connect account.




Compare and Protect

The Connect Admin Console is only available when you have a User Control or User & Data Control account on Connect. When you are installing only Compare or Protect and you only have a personal Connect account, you can create accounts for your users using the following link: http://workshare.force.com/knowledgebase/CustomerUploads.

To add users:

1. Click http://workshare.force.com/knowledgebase/CustomerUploads. This will display the following page:



- 2. Create a CSV file containing the user account information (up to 100 users). Ensure the file has the following mandatory headers: "email address" and "first name". You may also include the following headers: "last name", "job title" and "phone number".
- 3. Click **Choose File** and browse to where you have saved your CSV file with all your user details.
- 4. Select the file and click Open.
- 5. Enter your Connect login credentials in the Username and Password fields.
- 6. Click **Import**. The user details are added to your account and a registration email is sent to all the email address specified, inviting them to validate their Connect account.



DEPLOYMENT WITH ENTERPRISE LICENSE

When your users won't be using Connect functionality in Professional or you have restrictive firewall settings or you operate in a Citrix environment, enterprise licensing is recommended. An Enterprise license comes in the form of a Registry file that can be deployed across your network.

Contact Workshare Customer Support to request an Enterprise license. Workshare Customer Support will send you a Registry file that you can install on your machine by double-clicking. To install the license on your users' machines, deploy the Registry file across your network using your preferred method.

Note: You may receive two Registry files – one for Windows 32-bit environments and one for Windows 64-bit environments. Use the one appropriate to your environment.

Registry Location

Installing the REG file adds the license (adding keys and values) to the Registry in the following location:

- 32-bit: HKEY_LOCAL_MACHINE\Software\Workshare\Options\9.00\Internal\Subscription\ Features
- 64-bit: HKEY_LOCAL_MACHINE\Software\Wow6432Node\Workshare\Options\9.00\Internal\ Subscription\Features

Depending on the products purchased, one or both of the following keys are added – Compare and Protect. Each one includes a **Value** named "Feature" with the content of the license feature string set as the **Value data**.

End User Interaction

After deployment, the license will be installed in the Registry on each of your user's machines and they can use the Professional products. There will be no need for the end user to log in to Workshare Connect.

Capturing of Email

Enterprise licenses may capture a user's email address. If you do not want Workshare to capture the email addresses of your users at all, you should include the following switch with your install script.

CAPTURE_EMAIL

When this parameter is set to CAPTURE_EMAIL=NO, the install sets or updates the Workshare option in the Registry - **SubscriptionCaptureEmail** to **False**.

Note: This is an admin/HKLM only option In HKEY_LOCAL_MACHINE\SOFTWARE\Wow6432Node\ Workshare\Options\9.00\General\GeneralAdmin; it is not visible in WCM (Admin mode).


When the option set to **False**, Workshare does not send the user email address as part of the validation call for licensing and as a result a Connect account will not be provisioned.



RENEWING A LICENSE

When a trial license or a term license is coming to an end, a reminder is displayed to all users when they access any Workshare functionality.

One month before the license expires, a reminder (such as the example shown below) pops up on a daily basis alerting you as to when the license expires.



Proceed in any of the following ways:

- Click **Continue**. You can continue using Workshare functionality and the reminder will be displayed again on the following day.
- Click **Purchase now**. You are directed to the Workshare online store where you can purchase a new license.
- Select Don't show again and click Continue. You can continue using Workshare functionality and
 the reminder will not be displayed on a daily basis until 7 days before the expiry date when it will
 again be displayed on a daily basis.

Once you have renewed your license, Workshare will automatically refresh your users' licenses -- you don't need to redeploy a .REG file; your users don't have to sign in.

Note: If you have renewed your license and this notice is shown again, click **refresh** to update and validate your renewed license.



LICENSING

If you have restrictive firewall settings or if you are using a proxy server, whitelist or add the following domain name and port as an exception:

- *.workshare.com
- Port 443

If you do not renew your license before the expiry date, an expiry notice is displayed when you access any Workshare functionality.



Now you can either click **Purchase now** to purchase a new license or **Exit** to close the expiry notice. If you do not license your Workshare product, you will not be able to use any Workshare functionality.

Note: If you have renewed your license and this notice is shown again, click **refresh** to update and validate your renewed license.

Suppressing Expiry Reminders

If you want to stop users receiving license reminders so that only you (the administrator) receives a reminder, you can set the following Registry key.

HKEY_LOCAL_MACHINE\SOFTWARE\Workshare\Options\9.0\General\GeneralAdmin SuppressNag=true

The user will no longer receive a licensing reminder during the 30 days prior to expiry although if a license has expired and not been renewed, the user will still receive the expiry notice.



CHAPTER 4. CONFIGURATION

This chapter describes how to use the Workshare Configuration Manager to configure Workshare Professional/Compare/Protect. It includes the following sections:

- Introducing the Workshare Configuration Manager, page 33, provides an overview of the Workshare Configuration Manager and how you can use it to customize Workshare behavior to suit your organization's requirements.
- Accessing the Workshare Configuration Manager, page 35, describes how to access the Workshare Configuration Manager and its parameters.
- **Setting Parameters**, page 37, describes how to save configuration parameters to a configuration file as well as deploy the configuration file to other Workshare workstations.
- **Deploying Configuration Settings**, page 38, describes how to save policy sets and distribute them to other Workshare workstations.
- **Registry Configuration**, page 42, describes additional configuration performed directly in the Registry.



INTRODUCING THE WORKSHARE CONFIGURATION MANAGER

The Workshare Configuration Manager is a separate configuration utility that enables you to configure Workshare Professional/Compare/Protect and the way they behave as well as modify the configuration of the default profile (via the parameters in the Protection category).

Note: A profile is a set of policies which contain parameters applied by Workshare Protect when determining content risk.

Administrator Mode and User Mode

The Workshare Configuration Manager has two modes as follows:

- Administrator Mode: This mode should be used by administrators to make changes to the
 default settings on the local machine. Settings made are saved in HKEY_LOCAL_MACHINE in the
 Registry.
- User Mode: This mode should be used by users to make changes to the Workshare configuration
 to suit their own personal preferences on the local machine. Other users could log in and they
 would not have the same configuration settings. Settings made are personal to the user and
 saved in HKEY_CURRENT_USER in the Registry.

When Workshare is installed, the default configuration settings (factory defaults) are included in the installation and the Registry is empty of any of the Workshare Configuration Manager configuration settings. Once an administrator clicks **Apply to Local Machine** in the Administrator Mode of the Workshare Configuration Manager, the Registry (HKEY_LOCAL_MACHINE) is updated with any changes. Once an administrator clicks **Apply to Current User** in the Administrator Mode of the Workshare Configuration Manager, the Registry (HKEY_ CURRENT_USER) is updated with any changes. Additionally, when a user clicks **Apply** in the User Mode of the Workshare Configuration Manager, the Registry (HKEY_CURRENT_USER) is updated with any changes.

When determining what value to assign to each configuration parameter, or when generating the Client Default policy, Workshare looks in the following locations in the following order:

- HKEY_LOCAL_MACHINE just for the IgnoredUserOverrides key to see what parameters have been locked by the administrator
- 2. HKEY_CURRENT_USER
- 3. HKEY_LOCAL_MACHINE
- 4. WMOption.dll which contains an XML file with the factory defaults

It is important to remember that a user's preferences will take precedence over the default settings and the factory defaults. However, configuration parameters can be locked so that a user is unable to change the value of any given parameter.





You can use Administrator Mode of the Workshare Configuration Manager to establish global settings that standardize the use of Workshare across your organization. Once you have finalized the configuration, you can save the settings as an ADM or REG file and deploy to the Workshare workstations in your network. Refer to *Deploying Configuration Settings*, page 38.

Note: An ADM file is a group policy template file that can be rolled out using Group Policy. The ADM configuration file can be created using the Workshare Configuration Manager or you can use the ADM files supplied by Workshare.

The Workshare Configuration Manager can be installed as a standalone application if required. This would enable you to establish a global set of configuration parameters and deploy them company wide. As a standalone application, only the Administrator Mode of the Workshare Configuration Manager is available.

The Workshare Configuration Manager – User Mode will only show those options which are applicable to the modules which are currently configured for that user. The Administrator Mode will show all options for Workshare Professional, Compare and Protect regardless of which product is installed and what modules are configured.

Client Default Policy

When Workshare Protect is checking email attachments or open Microsoft Office documents for content risk or metadata, it uses the Client Default policy to determine if there is a risk.

Note: When Interactive Protect is configured, Workshare Protect checks email attachments against settings in the Registry.

The Client Default policy is a set of parameters configured in the Protection category of the Workshare Configuration Manager and saved in a file called WorkshareClient.runtimepolicy file.

The WorkshareClient.runtimepolicy file is automatically generated from the Registry in the following scenarios:

Action	Location of WorkshareClient.runtimepolicy
Workshare Installation	ProgramData/Workshare/PolicySets/ClientProfiles/Default
Re-running the Workshare Configuration Assistant	ProgramData/Workshare/PolicySets/ClientProfiles/Default
Applying changes in Administrator Mode of the Workshare Configuration Manager	ProgramData/Workshare/PolicySets/ClientProfiles/Default
Applying changes in User Mode of the Workshare Configuration Manager	Users/[current user]/AppData/Roaming/Workshare/ PolicySets/ClientProfiles/Default
Changing Registry values in the Registry which correspond to the Protection category options	Users/[current user]/AppData/Roaming/Workshare/ PolicySets/ClientProfiles/Default



Note: If you do not want the default policy files to be automatically regenerated in these scenarios, ensure the **Enable automatic generation of default profile** parameter (**Protection>Administration** category) is NOT selected. If this option is set off BEFORE the installation of Workshare, you must ensure you have created and placed your own security policy in the Client Default folder in the ProgramData/Workshare/PolicySets/ClientProfiles location.

When applying the Client Default policy, Workshare will look first in the User location (Users/[current user]/AppData/Roaming/Workshare/PolicySets/ClientProfiles/Default) and if it does not find a WorkshareClient.runtimepolicy file there, it will look in the Public location (ProgramData/Workshare/PolicySets/ClientProfiles/Default).

Note: If you want to create additional security policies, you should use Workshare Policy Designer and save each .runtimepolicy in a separate directory in ProgramData/Workshare/PolicySets/ClientProfiles.

ACCESSING THE WORKSHARE CONFIGURATION MANAGER

When the Workshare Configuration Manager is installed as a standalone application, only the Administrator Mode is available and it is accessed from the Start menu.

The Workshare Configuration Manager – User Mode can be accessed from within Microsoft Office or from the Start menu.

To access the Workshare Configuration Manager from Microsoft Office:

- 1. In Microsoft Office, click **Options** in the *Workshare* tab, **Options** group. The Workshare Configuration Manager opens in User Mode.
- 2. To access Administrator Mode, click Launch Administrator Mode.

To access the Workshare Configuration Manager from the Start menu:

- When the Workshare Configuration Manager is installed as a standalone application, from the Start menu, select All Programs > Workshare > Workshare Configuration. The Workshare Configuration Manager opens in Administrator Mode.
- When the Workshare Configuration Manager is installed as part of Workshare
 Professional/Compare/Protect, from the Start menu, select All Programs > Workshare >
 Workshare Configuration (User Mode). The Workshare Configuration Manager opens in User
 Mode. To access Administrator Mode, click Launch Administrator Mode.


To access the Workshare Configuration Manager from Workshare Compare:

- 1. Open Workshare Compare.
- From the Logo menu, select Configuration Manager. The Workshare Configuration Manager opens in User Mode.
- 3. To access Administrator Mode, click **Launch Administrator Mode**.

CONFIGURATION

In Administrator Mode, the state of the options reflects the settings in HKEY_LOCAL_MACHINE in the Registry.


Note: In order to access Administrator Mode, you must have local administrator rights. In Windows Vista and above, when UAC (user access control) is enabled, the User Access Control dialog is displayed when you click **Launch Administrator Mode**. If you do not have administrator rights, you can enter a user name and password to elevate you to administrator. If you do have administrator rights, you need to allow the Workshare Configuration Administrator Console (Workshare Configuration Manager) to access this computer. Click Yes and Administrator Mode is launched.



The configuration parameters for Workshare are grouped into categories (such as Protection, Comparison) and sub-categories (such as Administration, User Interface). In User Mode, categories are available according to your installation – Workshare Professional, Workshare Compare or Workshare Protect. Click a sub-category to display the parameters for that sub-category. The different sub-categories and their parameters are described in *Workshare Configuration Options*.

Searching Parameters

If you know the name of a parameter (or part of its name) but not its location, you can search the Workshare Configuration Manager using the search box on the top right.






Click the parameter in the results list and the relevant category and sub-category is displayed in the Workshare Configuration Manager.

SETTING PARAMETERS

Most parameters in the Workshare Configuration Manager are set by selecting or deselecting a checkbox. There are also some that require you to enter a value in a text box.

To specify parameters:

- 1. In the Workshare Configuration Manager, select a category and then a sub-category.
- 2. Set a value for a parameter by selecting or deselecting the checkbox or by entering a value in the text box.



3. Click the padlock icon to unlock/lock a parameter. When you lock a parameter, a user is not able to change the setting.

Note: The icon to the right of a parameter indicates that the parameter value has been changed. In Administrator Mode, the green arrow deployment icon is shown when a parameter will be included in a deployment script.

- 4. Continue to select categories and sub-categories and specify parameters as required.
- 5. Save your settings by clicking **Apply to Local Machine**. The Registry (HKEY_LOCAL_MACHINE) is updated with any changes.

A confirmation message is displayed once the settings have been saved.

6. Click OK.

Note: The icon is no longer displayed to the right of changed parameters but the green arrow deployment icon will remain.

Recipient Checking

You can specify different metadata removal settings for email attachments sent internally and externally. For example, you may want to remove all hidden data when sending emails externally, but only remove track changes and hidden text when emailing internally. Workshare Protect determines whether a recipient is external or internal as follows:



CONFIGURATION

Workshare Protect takes each recipient in the **To**, **Cc** and **Bcc** fields, and looks them up in the configured address book(s). Usually this is the contacts list or local address book (on your machine) and the global address book (on the server).

Note: To ensure that Workshare Protect can integrate with the local and global address books when users are offline, please refer to Chapter 4: Integration.

For each address there are three possible outcomes:

- The address does not exist in any address book. This is then processed as external.
- The address is a distribution list. In this case, the address of each member of the distribution list is checked.
- The address exists in one of the address books. If so, Workshare Protect does a further check that checks the type of address. Either it will be an Exchange\Notes address (meaning the address exists on the email server), or it will be an SMTP address (meaning the email will be routed via the Internet). If it is a server address, it is processed as internal. If it is an SMTP address, it is processed as external.

When deciding which metadata removal options to apply, each recipient is checked. If an external recipient is found, external metadata removal settings are applied. Only if all recipients are internal, are internal metadata removal settings applied.

Note: Using the **Treat the specified addresses as internal (Outlook)** parameter (**Protection** > **Administration** category), you can specify external email addresses that you would like to be treated as internal for the purpose of Workshare Protect applying policies.

DEPLOYING CONFIGURATION SETTINGS

In Administrator Mode, you can save the configuration settings as an ADM or REG file. This will enable you to distribute these settings to other machines without having to manually set the options on each machine. You set the configuration parameters for Workshare in a test installation or on any workstation with the Workshare Configuration Manager installed, save the configuration settings in an ADM or REG file and then deploy them to other Workshare workstations. This saves time and enables a consistency within your organization.

Additionally, you can save the configuration settings as a WSO file (Workshare Options file). A WSO file can be loaded in the Workshare Configuration Manager so you can restore the settings at some point in the future. This enables you to keep a work-in-progress or project file.

Finally, Workshare has created ADM files which contain all the options and their default values. These files are very similar to the files created by the Workshare Configuration Manager but contain placeholders for an unconfigured DMS server. Contact Workshare Customer Support for these files.




Saving Configuration Files

Configuration settings are saved in Administrator Mode of the Workshare Configuration Manager.

To save configuration settings:

- 1. In Administrator Mode of the Workshare Configuration Manager, specify configuration parameters as required. Refer to *Setting Parameters*.
- 2. Click the arrow on the **Save** button and select from the following:
 - Save as Workshare Options: To save the settings in a WSO file which can be loaded/opened in the Workshare Configuration Manager at a later time.
 - Save Deployment Script: To save the settings in an ADM or REG file which can be used to deploy to other workstations.
- 3. When selecting to save as a Workshare Options file, a Save As dialog is displayed.



4. Name the file as required, navigate to the save location and click **Save**. The settings are saved in a WSO file which can be loaded in the Workshare Configuration Manager at a later time.



5. When selecting to save as a deployment script, the *Deployment Script Settings* dialog is displayed.




- 6. From the **Environment** dropdown list, select your environment.
- 7. From the **Registry Target** dropdown list, select where in the Registry you want to save the settings.

Note: Selecting HKCU will replace any personalized settings configured by an individual user on this machine.

- 8. From the **Generate Script** dropdown list, select the type of file to generate. You can create a script:
 - For all options. The resulting ADM or REG file will contain all options. A REG file will set options that have been marked with the deployment icon and remove all other options by deleting them from the Registry. This will revert them to the factory default on the target machine. The ADM file will contain all the options and use the values defined by the Administrator as the default values. Typically this is used for new deployments it will generate a script that will set options that have been changed from the factory defaults and revert any unchanged options to the factory defaults on the target machine.
 - For options with a deployment icon. The resulting ADM or REG file will only contain those options indicated by a green deployment icon. No other options will be deployed or changed. Typically this is used when upgrading an existing deployment it will generate a script that will only set options that have been changed (indicated by the green arrow icon) and will not modify any unchanged options on the target machine.



9. In the Save Location field, click the browse button.



- 10. Name the file as required, navigate to the save location.
- 11. From the Save as type drop down list, select ADM File or Registry Script as the file type.
- 12. Click Save.
- 13. Click **Save** in the *Deployment Script Settings* dialog. The settings are saved to the specified ADM or REG file.

You can now deploy the REG file or use the ADM template to deploy settings to other individual Workshare workstations.

Loading Configuration Files

If you have saved the configuration settings as a Workshare Options (WSO) file, you can open the saved WSO file in the Workshare Configuration Manager. You can then update the settings on the local machine or continue developing a set of configuration parameters for future deployment. The save and re-load functionality enables you to keep a work-in-progress or project file.





To load a configuration file into the Workshare Configuration Manager:

- In Administrator Mode of the Workshare Configuration Manager, click the arrow on the **Load** button and select from the following:
 - Load Workshare Options: Enables you to browse to a WSO file.
 - Load Defaults: Resets all the parameters to their factory default settings.
 - Load User Settings: Resets all the parameters to the settings specified in the running user's HKEY CURRENT USER Registry hive.

Note: When you provide user credentials to the UAC prompt then that user is the running user.

The selected settings are displayed in the Workshare Configuration Manager.

Upgrading to Workshare 9

By default, when you deploy Workshare Professional/Compare/Protect to machines which have earlier versions of Workshare Professional/Compare/Protect, all existing settings and options are transferred – whether they are user settings or public settings. If you don't want to migrate the existing options and settings to the Workshare 9 installation, you must deselect the following parameters in the **General** > **Administration** category of the Workshare Configuration Manager:

- . Backup and migrate the configuration for the Current Users
- . Backup and migrate the default configuration for All Users

You must then save and deploy the configuration before installing Workshare 9. The installation of Workshare Professional will then install with only the default.

REGISTRY CONFIGURATION

This section describes configuration of Workshare that is done by making changes in the Registry.

Important: If you use Registry Editor incorrectly, you may cause serious problems that may require you to reinstall your operating system. Only system administrators should attempt to make changes in the Registry.

Small Text Removal

When Workshare is configured to clean/delete small text (smaller than 5 points), it will check content for half sizes as well as full sizes (4.5, 4, 3.5, 3, 2.5, 2, 1.5, 1, 0.5) and this may slow down the cleaning process. If you want Workshare to just clean full point sizes (4, 3, 2, 1), you need to create the Registry value <code>HalfPointSmallTextSupport</code> in the Registry key SOFTWARE\Workshare\Options\9.00\Protect \ProtectAdmin with a string value of <code>true</code>. Use <code>HKEY_LOCAL_MACHINE</code> to set an option machine-wide and <code>HKEY_CURRENT_USER</code> to set an option for a user.



CHAPTER 5. INTEGRATION

This chapter describes how to integrate Workshare with your email systems, DMSs and the Workshare OCR Server. It includes the following sections:

- Introduction, below, introduces integrating Workshare with your email systems and DMSs.
- **Document Management Systems Integration**, page 45, describes how to integrate Workshare with your Autonomy iManage, Hummingbird, Worldox, NetDocuments or SharePoint DMS.
- **Email System Integration**, page 62, describes how to integrate Workshare with your email system.



INTRODUCTION

Document Management Systems

Workshare Professional 9, Workshare Compare 9 and Protect 9 have been tested and certified in a number of DMS environments. If your environment is not included in the following list, it may still be a compatible environment. Contact Workshare Customer Support (support@workshare.com) for any help.

Note: Unless otherwise stated, all environments are the English version with the en-us language set.

DMS Integration:

Note: Check with your DMS vendor about which Windows operating system supports your DMS.

NetDocuments

Note: The NetDocuments integration requires that Microsoft Internet Explorer is installed (the NetDocuments login screen is displayed in an IE iframe) although it does not have to be the default browser.

Autonomy iManage:

- FileSite 9.2
- FileSite 9.0 Update 6
- FileSite 9.0 Update 5 (+ EMM)
- FileSite 8.5 SP3 Update 5/6
- DeskSite 9.2
- DeskSite 9.0 Update 6
- DeskSite 9.0 Update 5
- DeskSite 8.5 SP3 Update 5/6

• Open Text:

- eDOCS DM 10
- eDOCS DM 5.3.1 COM only (Patch 5)
- eDOCS DM 5.3 COM only (Patch 5 Rollup 4&5)

Worldox GX3

Note: Workshare recommends WBGX Version ID: 6EB.688.D48 (Mar 28 2014) 11.0 or later.

Workshare will endeavor to support future service packs of certified environments.



Email Systems

Workshare is certified with the following email systems:

- Microsoft Outlook 2013 SP1 (32 bit) + Japanese
- Microsoft Outlook 2013 (32 bit) + Japanese
- Microsoft Outlook 2010 SP2 (32 bit) + Chinese Simplified & French
- Microsoft Outlook 2007 SP3 (32 bit)
- IBM Lotus Notes 9.0.1
- IBM Lotus Notes 9.0

Note: Interactive Protect and the replace email attachment with link feature of Workshare Protect is not supported in a Lotus Notes environment.

During installation, Workshare automatically detects your email system and configures itself to work with that system. If you work with both Lotus Notes and Microsoft Outlook, Workshare is configured to work with Lotus Notes.

Workshare will endeavor to support future service packs of certified environments.

DOCUMENT MANAGEMENT SYSTEMS INTEGRATION

Autonomy iManage Integration - Configuring Server Integration

In order to use Workshare with an Autonomy iManage DMS, you must add the Workshare file types and the Workshare Compare application to the Autonomy iManage server so that the DMS can recognize and work with Workshare files. Additionally, it is necessary to add Workshare as an Autonomy iManage class.

Adding File Types to the Autonomy iManage Server

This step includes adding the Workshare Compare file type (WDF), the Combine in Workshare file type (WWB) and, if it is not already added, the Microsoft Word file type (DOC) to the Autonomy iManage server.


Note: This must be done for all Autonomy iManage databases, regardless of whether the user has permissions to a database or not.


To add file types to the Autonomy iManage server:

- In the Autonomy iManage Database Management window, expand the tree on the left underneath the database to be integrated with Workshare and select **Type**. A list of file types recognized by Autonomy iManage is displayed on the right side of the window.
- 2. From the Manage menu, select Add. The Add Type dialog is displayed.



3. Complete the fields as shown below and click **OK**.





Workshare Compare file type (WDF):

Combine in Workshare file type (WWB)

4. Ensure that the Microsoft Word file type (DOC) appears in the list of recognized file types. If it does not, complete the above steps to add it.

Adding the Workshare Compare Application to the Autonomy iManage Server


This step includes specifying the location of the Workshare Compare executable file as well as identifying the file types used by Workshare Compare. This is done for each Autonomy iManage database that will be used with Workshare Compare.

To add the Workshare Compare application to the Autonomy iManage Server:

- From the Start menu on the Autonomy iManage server, select Programs then Autonomy iManage Server and then Database Administration. The Autonomy iManage Database Management window is displayed.
- 2. Expand the tree on the left underneath the database to be integrated with Workshare and click **App Setup**. A list of applications set up to work with Autonomy iManage is displayed on the right side of the window.
- 3. From the Manage menu, select Add. The Add App Setup Entry dialog is displayed.



4. Complete the fields as shown below:



Note: Ensure the path points to the location of the Workshare Compare executable file. By default, this is **C:\Program Files\Workshare\Modules\DeltaVw.exe**.

5. Click OK.

Adding Workshare Professional as a Class to Autonomy iManage Server

Adding Workshare files as a class (Compare class and Workshare Combine class) in the Autonomy iManage server enables you to classify Workshare documents accordingly. This is done for each Autonomy iManage database that will be used with Workshare.


If you do not want to add the Compare class to your Autonomy iManage server, you can specify your own class for the WDF file. The class that you specify must exist on your server. Refer to the procedure, *To specify your own class*, page 48.

To add Workshare as a class:

- 1. In the *Autonomy iManage Database Management* window, expand the tree on the left underneath the database to be integrated with Workshare and select **Class**. A list of file classes defined in Autonomy iManage is displayed on the right side of the window.
- 2. From the *Manage* menu, select **Add**. The *Add Class* dialog is displayed.



3. Complete the fields as shown below and click OK.



Compare class

Workshare Combine class

•

<u>H</u>elp

To specify your own class:

Set the **Alternate Class Name** parameter in the Workshare Configuration Manager (**Integrations** > **Autonomy iManage** category). You set this parameter to specify the class that you want to use and enable it by selecting the **Use Alternate Class Name** parameter. The class MUST exist on your Autonomy iManage server.

Autonomy iManage Integration – Configuring Client Integration

There are several configuration procedures you may want to perform on an Autonomy iManage client when integrating with Workshare Professional, as follows:

- Launching Applications within Autonomy iManage
- Creating a Workshare Compare Icon on the Autonomy iManage Desktop




Launching Applications within Autonomy iManage

This procedure is only relevant when the Autonomy iManage server application location is different from your Local Application locations. Autonomy iManage would first use the local location of Workshare Compare before using the server location.

To launch Workshare Compare, Microsoft Word and Rich Text Format files from Autonomy iManage you have to add application information to Local Applications settings.

To add application information to Local Applications settings:

- 1. In the *WorkSite* ribbon in Outlook, select **Local Applications**. The *Application Setup Information* dialog is displayed.
- 2. Click the **Add** button. The *Add Local Application* dialog is displayed.
- 3. Complete the fields as shown below:



4. Click **OK** to save the changes.



Creating a Workshare Compare Icon on the Autonomy iManage Desktop

In order to launch Workshare Compare via an icon within your Autonomy iManage desktop, follow the procedure below.

To create a Workshare Compare icon:

- 1. Open Autonomy iManage.
- 2. Right-click the toolbar and select **Customize**. The *Customize* dialog is displayed.
- 3. Select the Commands tab.



4. Click and drag the **Workshare Compare** icon to the Autonomy iManage toolbar. The Workshare Compare icon now appears on the Autonomy iManage toolbar.

Autonomy iManage Integration - Configuring Workshare


On installation, Workshare automatically copies the Autonomy iManage server settings specified for the Autonomy iManage client. Workshare again retrieves the Autonomy iManage server settings at the beginning of each DMS session to keep the list of servers up to date.

If you do not use Autonomy iManage trusted login (so that each user has a unique user name and password to access the Autonomy iManage server), you must specify your Autonomy iManage user name and password in the Workshare Configuration Manager.



To specify/modify Autonomy iManage server settings:

1. In Administrator Mode of the Workshare Configuration Manager, select the **Integrations > Autonomy iManage** category.



To add details of a new server, click Add. An entry is added to the list of Autonomy iManage servers in the Servers section.



- 3. In the **Server Name** field, enter the name of your Autonomy iManage server.
- 4. In the UserID and Password fields, enter the user login details that enable login to the specified server. If you connect to your Autonomy iManage server using your Windows account, select the TrustedLogin checkbox only.
- 5. Select the **AutoLogin** checkbox to automatically connect to the server and authenticate the user at startup. If you do not select this checkbox, the server can be registered but will not be authenticated at startup. This may be useful in a multi-server environment when you want to save the overhead of authenticating all the servers at startup.

Note: If a document ID is passed to a Workshare product for a document on a server for which it has details (a registered server) but to which it is not connected, then the Workshare product will automatically connect to that referenced server.

6. Click **Test** to confirm connection to the specified server.



To delete a server from the list, click **Remove** to the right of the server details. To modify details of an existing server, edit the details in the **Servers** list.

Hummingbird Integration – DM5

In order to use Workshare with a Hummingbird DMS, you must add the necessary Workshare file types and identify Workshare Compare as an application in the DMS server so that the DMS can recognize and work with Workshare files. Additionally, the Workshare Professional, Workshare Compare and the Microsoft Word applications must be made 'compatible' with the Hummingbird DMS.


Note: The Hummingbird server integration procedures only need to be performed once per Hummingbird server. The procedures can be performed from the server or client machine.

Adding Application and File Types to the DM5 Server

This step includes adding the required file types used by Workshare - the Workshare Compare WDF file type and the Combine in Workshare WWB file type as well as specifying the location of the Workshare Compare executable file. The procedure described below is performed from the DM5 client machine.

To add application and file types to the DM5 server:

- 1. From the Start menu, select **Open Text > DM Server > Server Admin Tools > Library Maintenance**. The *Library Maintenance* window is displayed.
- 2. Click **Applications** and then click **New**. The *Application Maintenance* dialog is displayed.
- 3. Complete the fields as shown below:




Note: For PDF Combine, enter application/dcwin as the MIME Type.

Note: To add the file type, click the browse button and click **Add** in the dialog displayed. Enter **WDF** or **WWB** in the **Extension** field and **Workshare Deltafile** or **Workshare Combine** in the **Description** field and click **OK** and then **OK** again.

INTEGRATION



- 4. Click **OK**. The specified application now appears in the list of applications.
- 5. Double-click the new **DeltaView/Combine** entry to display the *Application Maintenance* dialog again.
- 6. Click the Launch Methods button. The Application Launch Methods dialog is displayed.
- 7. Click the **New** button. The *Application Launch Methods* dialog is displayed.



Note: If you already have Workshare DeltaView 2.9 or earlier configured, you should create a separate launch method for Workshare Compare.

- In the Location field, enter the location of the Workshare Compare/Combine executable file. By default, this is C:\Program Files\Workshare\Modules\DeltaVw.exe or Workshare.Pdf.Combine.exe.
- 9. In the **Command Line Parameters** field, %FULLPATH /PathEncode=powerDOCS.

Note: Do not forget to enter a space between FULLPATH and the forward slash.

- 10. From the **Integration** dropdown list, select **ODMA Compliant**.
- 11. Ensure the **Enabled** checkbox (top right) is selected.
- 12. Click OK, and then Close.




Making Workshare Compatible with DM5

In order for files created in Workshare to be retrieved from DM5, Microsoft Word and Workshare Compare must be made "compatible applications" with DM5.

To make Microsoft Word a compatible application:

- 1. In the Library Maintenance window, double-click DeltaView.
- 2. Click Compatible Apps. The Compatible Applications dialog is displayed.
- 3. From the **Non-Compatible Apps.** list, select **MS Word** and click **Add**. Microsoft Word is added to the **Compatible Apps.** list.



4. Click **OK**, and then **OK** again.

To make Workshare Compare a compatible application:

- 1. In the Library Maintenance window, double-click MS Word.
- 2. Click **Compatible Apps**. The *Compatible Applications* dialog is displayed.
- 3. From the **Non-Compatible Apps.** list, select **DeltaView** and click **Add**. Workshare Compare is added to the **Compatible Apps.** list.
- 4. Click **OK**, and then **OK** again.




Making the Workshare Compare Icon Appear on the Desktop and Within a User Profile

This section describes how to place the Workshare Compare icon on the DM5 desktop as well as within a user profile.

To add the Workshare Compare icon:

- 1. In the Library Maintenance window, double-click DeltaView.
- 2. Click Options. The Application Options dialog is displayed.



- 3. Select the Shows on Desktop and Valid on Profile checkboxes.
- 4. Click Close.

Worldox Integration – Configuring Compare Files


After installing Workshare Professional, you can configure the Worldox Compare Files option (available in the Worldox toolbar and the right-click menu) so that it works with Workshare.

To configure Compare Files in Worldox:


- 1. In Worldox, click **Compare Files** (in the toolbar or via the right-click menu).
- 2. Click **Properties** to the right of the **Compare using** field.



3. Click Add.



- 4. In the Compare Program Description field, enter a description such as "Workshare Compare".
- 5. Click Browse and browse to the Module folder in the Workshare installation folder.
- 6. Select Workshare. Worldox. Connector. exe and click OK.
- 7. In the Pass Parameters field, enter /original=%o /modified=%n.
- 8. Click OK.
- 9. Click Close.



Now you can run a comparison using Workshare Compare.

Once you have completed this configuration, right-clicking a file in Worldox or selecting a file and clicking **Compare Files**, will display the above dialog with Workshare Compare selected as the application to use for the comparison.



NetDocuments Integration


In order to maximize the integration of Workshare in NetDocuments, you should add Workshare as an application to your NetDocuments cabinets. Workshare will then be available when using the NetDocuments **Send to application** functionality.

To add Workshare as an application:


1. Click **Admin** in the top right of the NetDocuments window.



- 2. From the Cabinets list, click the cabinet you want to add Workshare to.
- 3. Click Integrate external applications at the top of the page.




4. A list of available published applications is displayed and you can select the app you want to be available in the *Send to Application* dialog.



- 5. Make sure Workshare Compare is selected, scroll down and click **Save**.
- 6. Scroll to the bottom of the cabinet page and click **Submit**.



Now when a user selects the **Send to application** option in NetDocuments, **Workshare Compare** is listed as an available application.



Note: If there is a "Workshare" entry, it should not be used. Users should select **Workshare Compare** to ensure access to complete Workshare functionality.

You can remove the "Workshare" entry from the Send to Application dialog by removing the following Registry key:

HKEY_CLASSES_ROOT\DeltaView.Application

WARNING! Removing this Registry key affects the behavior of the Workshare API. If you use the Workshare API, you are recommended NOT to remove this key.

SharePoint Integration - Server Installation

In order to use Workshare with SharePoint, the Workshare Professional Extension for SharePoint must be installed on Microsoft Windows Server 2008 (or later) running Microsoft Windows SharePoint Services 3.0 (or later).

Before beginning the installation procedure, make sure that all other programs are closed and disable any anti-virus software.



To install Workshare Professional Extension for SharePoint:

1. Locate the installation package Workshare.Connect.SharePoint.WebService.x64/x86.msi and double-click to start the installation wizard. The installation welcome screen is displayed.



2. Click Next.






INTEGRATION

- Select the bin folder in the SharePoint virtual directory where Workshare Professional Extension for SharePoint will be installed. By default this is located at C:\Inetpub\wwwroot\wss\VirtualDirectories\ 80\bin.
- 4. Click Next.



- 5. Select the SharePoint ISAPI directory where the Workshare Professional Extension for SharePoint web services will be installed. By default, this is located at C:\Program Files\Common Files\Microsoft Shared\web server extensions\12\ISAPI\.
- 6. Click Next.





- 7. Click **Next** to begin installation or click Back button to change any installation settings.
- 8. Once the installation has completed, click **Finish**.

SharePoint Integration - Client Configuration

The SharePoint Integration for Workshare is provided as part of the Workshare installation package and requires a small amount of configuration on the client to specify SharePoint sites and servers that will be accessed from Workshare.

SharePoint Site Configuration

When comparing documents, users can select documents from a SharePoint site. The sites available for selection have to be configured in the Workshare Configuration Manager.

To configure SharePoint sites:

- 1. In Administrator Mode of the Workshare Configuration Manager, select the **Integrations** > **Microsoft SharePoint** category.
- 2. Click Add. An entry is added to the list of SharePoint sites in the Servers section.



3. In the text box, enter the complete URL for the SharePoint site location.





- 4. From the Metadata Cleaning Policy dropdown list, select how the site is to be considered for policy application purposes. If you select Internal Cleaning Policy, documents at the specified SharePoint site will be treated similarly to documents emailed internally. If you select External Cleaning Policy, documents at the specified SharePoint site will be treated similarly to documents emailed externally.
- 5. Click **Test** to confirm connection to the specified site.

To delete a site from the list, click **Remove** to the right of the site details. To modify details of an existing site, edit the details in the **Servers** list.

EMAIL SYSTEMS INTEGRATION

Workshare uses the mail server address book to determine if recipients are internal or external, and applies particular settings as a result. Therefore if you want to use Workshare Protect to protect your documents while working offline, you need to ensure your machine is set up to enable recipients to be resolved correctly.

If a copy of your mail server address book is not available locally, all recipients are treated as external. The following sections describe how to create a local copy of your mail server address book in different email clients.

Setting Up Microsoft Outlook

For Workshare Protect to work correctly with Microsoft Outlook in offline mode, you simply need to enable offline mode (as specified in the Microsoft Outlook documentation), and ensure that you download the server address book.

To download the server address book:


- 1. From the *Tools* menu, select **Send/Receive** and then **Download Address Book**.
- 2. Select to download the address book.
- 3. Select to download full details.
- 4. Ensure the correct server address book is selected.



Setting Up IBM Lotus Notes

Resolving Email Addresses as Internal - Creating the Internal Domain List

Workshare categorizes the routing of email messages as either Internal or External to determine which policies to apply. Internal addresses are identified based on the recipient's domain. For Workshare to recognize the domain as internal, the internal domain list need to be populated with the value of the recipient's domain as it appears on the person's detail page in the Domino directory.



To set the internal domains:

The Internal Domain List can be set in the Workshare Configuration Manager (**Protection** > **Administration** category). If more than one domain is required then the values should be separated with a semicolon (;), for example, "Domain 1;Domain 2". The value is not case sensitive.

Offline Mode

For Workshare Protect to work correctly with Lotus Notes in offline mode, you need to set up the client to work offline (as specified in the Lotus Notes documentation), and set up the Mobile Directory Catalog on the Lotus Domino server. You must then replicate the Mobile Directory Catalog on the Lotus Notes client.

INTEGRATION



Setting Up the Mobile Directory Catalog on the Lotus Domino Server

This step involves creating the database (Mobile Directory Catalog), configuring the database and then loading the database.

To create the Mobile Directory Catalog:

- 1. From the File menu, select Database and then New.
- 2. Next to Server, select the Dircat server you picked to aggregate the directory catalog.
- 3. Next to **Title**, enter a title for the directory catalog (**Mobile Directory Catalog**).
- 4. Next to **Filename**, enter a file name for the catalog ('MobileDC.nsf').
- 5. Select Create full text index for searching.
- 6. Change 'Template Server...' to Domino server.
- 7. Select Show advanced templates.
- 8. Below **Template server**, select a server that stores the Directory Catalog template, and then click **OK**.
- 9. Select the **Directory Catalog (DIRCAT5.NTF)** template.
- 10. Click OK.

To configure the Mobile Directory Catalog:

- 1. In the database you created (Mobile Directory Catalog), select Create and then Configuration.
- 2. Complete the following fields in the Directory Catalog Configuration document:
 - Change Directories to include to include the Domino Directories the Direct task aggregates (Names.nsf).
 - Change Additional fields to include to include MailSystem.
- 3. Click Save and Close.

To load the Mobile Directory Catalog:

 From the Lotus Domino Server Administrator run the command Load Dircat database to build the condensed Directory Catalog (Load DirCat MobileDC.nsf).

Replicating the Mobile Directory Catalog on the Lotus Notes Client

This step involves replicating the Mobile Directory Catalog on the Lotus Notes client and setting up the client to use the Mobile Directory Catalog for name resolution.

To replicate the Mobile Directory Catalog:

- 1. From the File menu, select **Database** and then **Open**.
- 2. In the *Open Database* dialog, change the **Server** to the Domino server and the **Database** to Mobile Directory Catalog and click **Open**.
- 3. While the Mobile Directory Catalog database is open, from the *File* menu, select **Replication** and then **New Replica**.



INTEGRATION

4. Verify that the server is **Local** and the file name and title is for the Mobile Directory Catalog (**MobileDC.nsf**) and click **OK**.

To set up the client to use the Mobile Directory Catalog for name resolution:

- 1. From the File menu, select Preferences and then User Preferences.
- 2. Select Mail and News.
- Modify the Local Address Books and add the Mobile Directory Catalog to the existing list (names.nsf, MobileDC.nsf).
- 4. Click OK.

Note: This step can only be completed if the Mobile Directory Catalog exists. See Setting Up the Mobile Directory Catalog on the Lotus Domino Server, page 64.

Issues with Custom Forms (Recipient Fields)

If you work with custom forms and you modify recipients, you should be aware of which address fields Workshare Protect uses to resolve recipients as internal or external.

In order to determine the internal/external classification of a destination, only the following fields relating to recipients are extracted from the form by the EM_MAILSENDNOTE event:

- EnterSendTo
- EnterCopyTo
- EnterBlindCopyTo

If you use custom forms, you should note that the fields **Recipients**, **SendTo**, **CopyTo** and **BlindCopyTo** are not resolved.



CHAPTER 6. NETWORK DEPLOYMENT

This chapter describes how to install and license Workshare across your network. It includes the following sections:

- Overview, below, introduces the options available for installing Workshare across a network.
- **Deploying via the Command Line**, page 68, describes the steps required to use the command line to install and license Workshare across your network.
- Citrix Installation Guidelines, page 75, describes how to install Workshare on Citrix.
- Active Directory Deployment Guidelines, page 76, describes how to deploy Workshare using Active Directory.



OVERVIEW

Deploying Workshare across your network means installing your Workshare products on all workstations in your network. Workshare can be deployed across your network using the Workshare command line installation or third party deployment products.

If you want to deploy specific configuration settings with Workshare, you must use a REG file or an ADM template. Refer to *Chapter 3: Configuration*. It is recommended to deploy the configuration settings prior to the Workshare installation.

If you are licensing using the User Authenticated method, there is no need to include a license file in the deployment. The first time your users access Workshare functionality, they are prompted to log in to Workshare Connect and their license entitlements are retrieved and assigned automatically.

If you are licensing using the Enterprise method, you will need to obtain a Registry file from Workshare Customer Support and you must deploy this to license your users. This Registry file can be included in your deployment script.

The executables download prerequisites from the Internet if they are required. For enterprise deployments, the prerequisites can be extracted from the executables using the /layout command. Refer to Windows Installer Packages.

Installation File Summary

The installation requires the following prerequisites:

Prerequisite	Version	os	Office	Notes
Microsoft .NET Framework 4.5	4.5.50709.17929	Windows 7, Server 2008, Server 2008 R2	NA	
Microsoft Visual C++ 2012 Redistributable Package (x86)	11.0.61030.0	All (including x64 versions)	NA	
Microsoft Visual C++ 2012 Redistributable Package (x64)	11.0.61030.0	x64 OS versions	NA	The right-click handler is written in x64 code and requires this prerequisite.
Microsoft Visual Studio 2010 Tools for Office Runtime Setup	10.0.40303.00	All	All	This prerequisite is required to run Microsoft Office based solutions built using Microsoft Visual Studio 2010, 2012, and 2013. Visual Studio itself is NOT required to install Workshare.



Note: Microsoft .NET Framework should be installed first. The other prerequisite components can be installed in any order.

For further information about each prerequisite, refer to Appendix C: Workshare Prerequisites.

The extracted files include the following Workshare MSI packages:

Executable	Contents Extracted
Workshare.Professional.Bundle.exe	Workshare.Professional.msi
	WorkshareCompareForPowerPoint.msi
	Workshare.Desktop.msi
	Redist folder including the prerequisite executables (dotNetFx45_Full_x86_x64.exe, vcredist_x64.exe, vcredist_x86.exe, vstor_redist.exe)
Workshare.Compare.Bundle.exe	WorkshareCompare.msi
	WorkshareCompareForPowerPoint.msi
	Workshare.Desktop.msi
	Redist folder including the prerequisite executables (dotNetFx45_Full_x86_x64.exe, vcredist_x64.exe, vcredist_x86.exe, vstor_redist.exe)
Workshare.Protect.Bundle.exe	WorkshareProtect.msi
	Workshare.Desktop.msi
	Redist folder including the prerequisite executables (dotNetFx45_Full_x86_x64.exe, vcredist_x64.exe, vcredist_x86.exe, vstor_redist.exe)

All Workshare products are installed on a per machine basis.

DEPLOYING VIA THE COMMAND LINE

You can use the executable file or the MSI files found within the executable file to install Workshare from the command line.

Configuring Modules During Installation

In a Workshare Professional installation, the Compare, Protect and Connect modules (products) are installed by default and additionally, Microsoft Office integration is installed by default. During the command line install, you can customize the module selection by setting Registry values.

In a Workshare Compare installation, the Compare module is hard-coded into the installation and Microsoft Office integrations is installed by default. During the command line install, you can customize the Connect, Office and DMS integration selection by setting Registry values. You cannot customize the Compare module.

Workshare

NETWORK DEPLOYMENT

In a Workshare Protect installation, the Protect module is hard-coded into the installation and the Connect, Office and DMS integrations are installed by default. During the command line install, you can customize the Connect and Office integration selection by setting Registry values. You cannot customize the Protect module selection.

Registry

The Registry location HKEY_LOCAL_MACHINE\SOFTWARE\Workshare\Install contains DWORD values which can define the module state.

Module	Registry Value	DWORD Value	Available In
Autonomy iManage	nage ProfInterwovenModule		Professional, Compare & Protect
Compare	ProfCompareModule	1	Professional
Connect	ProfConnectModule	1	Professional, Compare & Protect
Hummingbird	ProfHummingbirdModule	1	Professional, Compare & Protect
Microsoft Excel Integration	OfficeExcelIntegration	1	Professional, Compare & Protect
Microsoft Outlook Integration	OfficeOutlookIntegration	1	Professional, Compare & Protect
Microsoft PowerPoint Integration	OfficePowerPointIntegration	1	Professional, Compare & Protect
Microsoft Word Integration	OfficeWordIntegration	1	Professional, Compare & Protect
NetDocuments	ProfNetDocumentsModule	1	Professional, Compare & Protect
Worldox	ProfWorldoxModule	1	Professional, Compare & Protect
Protect	ProfProtectModule	1	Professional
SharePoint	ProfSharepointModule	1	Professional, Compare & Protect

For instance, the following example Workshare Professional Registry script would enable Compare and Protect and Connect and NetDocuments and disable SharePoint, Hummingbird, Autonomy iManage and Worldox:

Windows Registry Editor Version 5.00

[HKEY_LOCAL_MACHINE\SOFTWARE\Workshare\Install]

"ProfCompareModule"=dword:0000001



NETWORK DEPLOYMENT

```
"ProfProtectModule"=dword:00000001

"ProfConnectModule"=dword:00000000

"ProfHummingbirdModule"=dword:00000000

"ProfInterwovenModule"=dword:00000000

"ProfSharepointModule"=dword:00000000

"ProfNetDocumentsModule"=dword:00000001

"ProfWorldoxModule"=dword:00000000
```

Information in a Registry script can be imported into the Registry using regedit.exe. Assuming that the above Registry script is in WorkshareModuleState.reg, you could import it into the Registry silently by:

Regedit /s <path to shared directory>\WorkshareModuleState.reg

DisableFeatures.ini

The DisabledFeatures.ini file is no longer supported for installations of Workshare.

In previous versions of Workshare, the module state could be controlled with an INI file called **DisabledFeatures.ini** in the installation directory. This INI file has no effect on the installation.

Installation Procedure with the Install Wizard

The Workshare install contains the Workshare Install Wizard and Workshare installs. The Workshare Install Wizard examines the client desktop, downloads any prerequisites not present, installs the prerequisites and installs and configures the Workshare installs.

Deploying Workshare with the Executable

As an example, the following procedure describes how to install Workshare Professional using the **Workshare.Professional.Bundle.exe** executable.

To install Workshare using the executable:

- 1. Create a shared directory with relevant permissions so that client machines can access the Workshare executable during the installation.
- 2. Copy the executable to the shared directory.
- 3. The default module state is to install the Compare, Protect and Connect modules. You can change the installed module state by running a Registry script on the client to set the required module install state before installing the executable.
- 4. Run the executable on the client desktop. This will extract the files to the client and run the Install Wizard on the client machine. Parameters passed to the executable are passed on to the Install Wizard. The command line is:

```
<path to Workshare.Professional.Bundle.exe > [/silent]
```



Installation Procedure using the MSI Files Directly

To install Workshare using the MSI files you must extract the contents of the Workshare executable using the /layout command and ensure that all prerequisites are installed on the client desktop.

For MSIs you must specify msiexec.exe /i [InstallerPath] [InstallerArgs].

To deploy Workshare using MSIs:

- 1. Create a shared directory with relevant permissions so that client machines can access the Workshare installation files during the installation.
- 2. Run Workshare.Professional.Bundle.exe /layout and this will extract and download the prerequisites and MSIs to a folder called Redist to the directory created in step 1.
- 3. The default module state is to install the Compare, Protect and Connect modules. You can change the installed module state by running a Registry script on the client to set the requested module install state before running the MSI. Alternatively, you can specify modules to install to the Professional MSI in step 5.
- 4. Install prerequisites (downloaded in Step 2).
- 5. Install the product (Workshare.Professional.msi, WorkshareCompare.msi, WorkshareProtect.msi).
- 6. (Optional) Install the Compare for PowerPoint msi (WorkshareCompareForPowerPoint.msi).
- 7. (Optional) Install the Desktop msi (Workshare.Desktop.msi).

In order to deploy Workshare with specific configuration settings, you must use a REG file or an ADM template. Refer to *Deploying Configuration Settings*. If you are using an Enterprise license, you can include the license REG file in your script.

Note: The Workshare MSIs must be installed in the order specified above.

First Example Installation

The following example will install Workshare Professional for the first time with the Compare, Protect and Connect modules enabled on an x64 system, quietly. This is done from the command line or using a batch (.bat) file and should only be attempted by the network administrator or other qualified personnel. It assumes that the files have been extracted to a shared directory.

To install Workshare:

1. Enter the following command to install the Professional Client quietly:

msiexec.exe /i <path to shared directory>\Workshare.Professional.msi
REINSTALL=ALL REINSTALLMODE=vomus ALLUSERS=1 SKIP_UPGRADE_WARNING=1
cproperty1> property...> /qn

2. Enter the following command to install Compare for PowerPoint quietly:

msiexec.exe /i <path to shared directory>\
WorkshareCompareForPowerPoint.msi REINSTALL=ALL REINSTALLMODE=vomus
ALLUSERS=1 /qn



NETWORK DEPLOYMENT

3. Enter the following command to install Workshare Desktop quietly:

msiexec.exe /i <path to shared directory>\Workshare.Desktop.msi
MSIINSTALLPERUSER= ALLUSERS=2 ENABLEUPDATES=0 /qn

Note: If you want to turn logging on during the install, add /I*v <path and name of log file> before /qn. This generates a Windows Installer verbose (descriptive) log file which can be useful should you need to contact Workshare Customer Support.

As an alternative to installing quietly (/qn) use /qn+ to perform a silent install with final notification.

Refer to *Appendix A: Additional Msiexec.exe Parameters and Switches*, for additional parameters and switches that can be passed to the msiexec.exe.

Second Example Installation

The following example will silently install Workshare Professional for the first time with the Compare module only enabled on a system which has all prerequisites installed. It will also license Workshare Compare. This is done from the command line or using a batch (.bat) file and should only be attempted by the network administrator or other qualified personnel.

To install Workshare:

Enter the following command to install the Professional Client quietly:

msiexec.exe /i <path to shared directory>\Workshare.Professional.msi
REINSTALL=ALL REINSTALLMODE=vomus ALLUSERS=1 SKIP_UPGRADE_WARNING=1
INSTALL COMPARE=1 /qn

Note: If you want to turn logging on during the install, add /I*v <path and name of log file> before /qn. This generates a Windows Installer verbose (descriptive) log file which can be useful should you need to contact Workshare Technical Support.

To license Workshare:

regedit.exe /s "<path to reg file location>/<name of reg file>"

Refer to Appendix A: Additional Msiexec.exe Parameters and Switches, for additional parameters and switches that can be passed to the msiexec.exe.

Compulsory Properties - Professional/Compare/Protect

The following table shows the compulsory properties that must be specified for installation of Professional/Compare/Protect.

Property	Value
REINSTALL	Ensures that upgrades install correctly. The required value is ALL .
REINSTALLMODE	Sets the reinstall mode for upgrades. The default value is vomus . This ensures that the latest versions of the MSI packages are cached and older files are overwritten.



Property	Value	
ALLUSERS	Installs the application per machine. The required value is 1.	
INSTALLDIR	Specifies the installation folder for Workshare. If this property is not specified, the default value is used which is <programfilesfolder>\ Workshare\Modules</programfilesfolder>	
SKIP_UPGRADE _WARNING	Disables the display of the upgrade warnings when installing Workshare. Required for silent installations. The required value is 1.	

Optional Properties – Professional/Compare/Protect

The following table shows the optional properties that can be specified to the Workshare install (Professional/Compare/Protect).

Property	Value
LOGFILE	Name and location of the WCA log file. For example, LOGFILE="C:WorkshareConfig.log". The log file can either be stored at a shared location or stored locally on the workstation. If a location is not specified for the log file it will be written to the local TEMP folder. By default the log file is named WorkshareConfig.log. The WCA log file will provide details of all the steps the WCA has taken and can be passed to Workshare if any difficulties are encountered.
	The log file is appended to, not overwritten, in order to retain all logged information. Therefore the latest details will be at the end of the log file.
NOTESINIFILE_PATH	Location of the notes.ini file. This should be specified in non-standard IBM Lotus Notes environments to ensure that Workshare components are added correctly to the INI file by the install.
INSTALL_COMPARE	Turns Compare module on. To enable installation of the Compare module, set INSTALL_COMPARE=ON.
INSTALL_CONNECT	Turns Connect module on (Save/Share from Office and Compare and Connect panel). To enable installation of the Connect module, set INSTALL_CONNECT=ON.
INSTALL_DVSHORTCUT	Installs the Workshare Compare shortcut on the desktop. The shortcut is created by default. To prevent the creation of the shortcut set INSTALL_DVSHORTCUT=OFF
INSTALL_HUMMINGBIRD	Turns Hummingbird module on. To enable installation of the Hummingbird module, set INSTALL_HUMMINGBIRD=ON.
INSTALL_INTERWOVEN	Turns Autonomy iManage module on. To enable installation of the Autonomy iManage module, set INSTALL_INTERWOVEN=ON.
INSTALL_PROTECT	Turns Protect module on. To enable installation of the Protect module, set INSTALL_PROTECT=ON.



Property	Value
INSTALL_SHAREPOINT	Turns SharePoint module on. To enable installation of the SharePoint module, set INSTALL_SHAREPOINT=ON.
INSTALL_NETDOCUMENTS	Turns NetDocuments module on. To enable installation of the NetDocuments module, set INSTALL_NETDOCUMENTS=ON.
INSTALL_WORLDOX	Turns Worldox module on. To enable installation of the Worldox module, set INSTALL_WORLDOX=ON.
INSTALL_EXCEL_ INTEGRATION	Integrates Workshare into Microsoft Excel. To enable installation of the Microsoft Excel integration, set INSTALL_EXCEL_INTEGRATION=ON.
INSTALL_OUTLOOK_ INTEGRATION	Integrates Workshare into Microsoft Outlook. To enable installation of the Microsoft Outlook integration, set INSTALL_OUTLOOK _INTEGRATION=ON.
INSTALL_POWERPOINT_ INTEGRATION	Integrates Workshare into Microsoft PowerPoint. To enable installation of the Microsoft PowerPoint integration, set INSTALL _POWERPOINT_INTEGRATION=ON.
INSTALL_WORD_ INTEGRATION	Integrates Workshare into Microsoft Word. To enable installation of the Microsoft Word integration, set INSTALL_WORD_INTEGRATION=ON.
CAPTURE_EMAIL	Sets or updates the Workshare option SubscriptionCaptureEmail in the Registry. When CAPTURE_EMAIL=FALSE , Workshare does not send the user email address as part of the validation call for licensing and as a result a Connect account is not provisioned. Refer to <i>Capturing of Email</i> for more information.

Note: Properties and values are all case sensitive. The use of "" should be used where there is character spacing in file paths.

If none of the Compare, Protect or Connect module properties is specified, the Compare, Protect and Connect modules will be installed. If any of the Compare, Protect or Connect module property are specified, then unspecified modules are not installed.

If none of the Microsoft Office integrations is specified, then all integrations are installed and Workshare will integrate with Microsoft Word, PowerPoint, Excel and Outlook. If one of the Microsoft Office integrations is specified, then the others are assumed to be "off" unless specifically specified as "on".



Optional Properties – Desktop Client

The following table shows the optional property that can be specified to the Workshare Desktop Client install.

Property	Value
UPDATE_CONTROL	Specified how updates are managed. You can specify a value as follows:
	0 – automatically download and install updates (default)
	1 – notify user when updates are ready to install
	2 – do not download or install updates
	If this property is not specified then the Desktop Client will automatically download and install updates.

CITRIX INSTALLATION GUIDELINES

Workshare can be installed on a Citrix server using the standard installation process. To restrict the number of users who have access to Workshare, you are required to manually modify the Registry keys.

Note: Workshare is configured to install on a per machine basis and not a per user basis.

To install Workshare on the Citrix server:

- 1. Ensure the Terminal Server is in Install mode.
- 2. Install Workshare on the Citrix server using the standard installation process. It is recommended that the default folder structure: "Program Files/Workshare/Modules" is retained. Refer to Chapter 2: Installation on a Single Workstation, more information.
- 3. Remove any shortcuts from the desktop if they were created.

The above steps will install Workshare for all users of the Terminal Server. To customize access to Workshare functionality, use the following approach:

Enable Specific Users: Remove Workshare integration from all Microsoft Office applications and then use a logon script deployed to specific users (using Active Directory) to reconfigure the Workshare integration when needed/necessary.

Note: When the installation remains a per machine install, all users using the Citrix server where Workshare is installed will get Workshare. This may not be required and it will increase the load on the server.



Enable Specific Users

These steps are best performed immediately after installation of Workshare Professional/Compare/Protect. You can find the Citrix reg files needed for this procedure (CitrixProfessionalDisable LocalMachine.reg, CitrixProfessionalDisableUser.reg and CitrixProfessionalEnableUser.reg) in the Modules folder.

To disable Workshare for all Microsoft Office users:

- Remove All Users/Current User Registry settings as follows: Execute CitrixProfessionalDisableLocalMachine.reg/CitrixProfessionalDisableUser.reg.
- Manually remove Workshare Batch Clean.lnk (if Workshare Protect is enabled) from All
 Users/Current User [SendTo] folder, so that the corresponding context menu items in right click
 > Send to are removed.

To enable Workshare Professional for individual Microsoft Office users:

- 1. Enable Current User Registry settings as follows: Execute CitrixProfessionalEnableUser.reg.
- 2. If you have Workshare Protect enabled, run Workshare.Protect.UserInit.exe to bring back Workshare Batch Clean.Ink.

ACTIVE DIRECTORY DEPLOYMENT GUIDELINES

When working with Windows 2008 Server (or later), you can deploy Workshare across your network using Active Directory. "Assigned to machine" installation is the preferred method of distributing Workshare Professional via Active Directory and is described in *Deploying Workshare Professional/Compare/Protect*, page 77. Workshare Desktop can be distributed on a "per user" or "per machine" basis and this is described in *Deploying Workshare Desktop*, page 82.

The "assigned to user" and "published to user" methods are outlined below.

Assigned/Published to User Methods

In general, it is not recommended to deploy Workshare Professional/Compare/Protect using the assigned to user or published to user methods. These methods do not complement the way Workshare works for the following reasons:

- If all previous installations of Workshare were assigned to machine installs, a subsequent assigned/published to user install will not remove previous versions of Workshare.
- The Workshare application is not designed to support user isolation for either assigned or
 published to user in Active Directory deployment. Whilst Workshare will operate normally for the
 user for which it is installed, it will also be partially visible to other users other users on the
 machine will see the Workshare menu but will not be able to use it. If an application has been
 assigned or published to a user, another user should not be able to see it or operate it at all.

Note: With Workshare, another user has the Workshare menu and button (not the Workshare Panel) in Microsoft Word but when a menu option or the button is clicked, the error: "WinWord.exe Unable to perform request: Unexpected exception" is displayed.

Workshare

NETWORK DEPLOYMENT

Workshare Desktop can be deployed using the assigned to user, published to user or assigned to machine methods.

The published to user method does not install the software but it installs 'entry points' so that it looks to the user like the software is installed. However, the software is not installed until it is used - when an 'entry point' is activated, the software is installed. An 'entry point' can be things like a desktop shortcut, a start menu shortcut, a file extension or a template.

For example, if publishing Adobe Acrobat to a user, the following would happen:

- Shortcuts are placed wherever Adobe Acrobat has assigned its shortcuts (such as the desktop and start menu).
- File extension associations for PDF are linked to Adobe Acrobat.
- The software will then install if the user either attempts to click on one of the shortcuts or attempts to open a .PDF.

The published to user method uses a technology called JIT (just-in-time). This enables an administrator to deploy the software to every user (for example) and the software will only be actually installed to the users that require it. This saves on bandwidth, licensing and workstation disk space.

With Workshare Professional/Compare/Protect, there are no valid entry points.

- There are no shortcuts that users click on to launch Workshare (it is opened via Microsoft Word).
- Workshare does not have a file extension other than W3 files but users will not be opening these
 files.

The only feature that will work with published to user is the "add new software" entry under add/remove programs.

Deploying Workshare Professional/Compare/Protect

Note: Before installing using this method, please refer to the section, Deploying via the Command Line, page 68.

If you want to deploy specific configuration settings with Workshare, you must use a REG file or an ADM template. Refer to *Chapter 3: Configuration*.

If you are using an Enterprise license, you must include the license REG file in your script.


The following procedure must be completed for each of the installation components of Workshare – Workshare.Professional.msi/WorkshareCompare.msi/WorkshareProtect.msi/WorkshareCompareForPow erPoint.msi. The following example illustrates how to create the Workshare.Professional.msi Active Directory group policy.

To deploy Workshare Professional using Active Directory:

- 1. On the Windows Server machine, create a shared folder with relevant permissions so that client machines can access the Workshare MSI during the automatic installation.
- 2. Extract the MSI file from the EXE install file and copy it into the folder created in step 1.




- Create a transform (MST) file. The transform file is used to specify properties, such as INSTALLDIR, during the installation. The following procedure describes how to create a transform file using the Orca utility provided in the Windows Installer Software Developers Kit.
- 4. Launch Orca.
- 5. Open the Workshare.Professional.msi file.



6. From the *Transform* menu, select **Generate Transform** and the save the transform file to the shared folder created in step 1.



7. From the Start menu, launch **Active Directory Users and Computers**. A list of organizational units is displayed on the left side.



- 8. You now have to configure a group policy for the users to which you will deploy Workshare Professional. This is done for each organizational unit that includes users to which you want to deploy.
- 9. Right-click an organizational unit and select **Properties**.




10. In the Group Policy tab, click the New button and enter a name for the new policy.




- 11. Select the new policy in the upper area and click the **Properties** button.
- 12. In the **Security** tab, click **Add**. A list of users in the organizational unit is displayed.
- 13. For all users to which you will deploy Workshare Professional, ensure that at a minimum the following permissions are selected:
 - □ Read
 - Apply Group Policy
- 14. For any users to which you do not want to deploy Workshare Professional, ensure that the **Apply Group Policy** permission is not selected.
- 15. Click **OK**.
- 16. In the **Group Policy** tab, select the policy in the upper area and click the **Edit** button. The *Group Policy* window is displayed.



17. Expand the **Computer Configuration** tree and the **Software Settings** node.




- 18. Right-click Software installation and select New then Package.
- 19. Browse to the shared folder and select the Workshare.Professional.msi/ WorkshareCompare.msi/WorkshareProtect.msi/WorkshareCompareForPowerPoint.msi file.
- 20. Click Open. The Deploy Software dialog is displayed.



- 21. Ensure that the **Advanced published or assigned** option is selected and click **OK**.
- 22. In the Modifications tab, click Add.
- 23. Browse to the transform (MST) file created in steps 4 to 13 and click Open.
- 24. Click **OK**.
- 25. In the *Group Policy* window, expand the **Administrative Templates** node and then the **Windows Components** node.
- 26. Select Windows Installer.



- 27. On the right side of the Group Policy window, double-click Logging.
- 28. Select the **Enabled** radio button and in the **Logging** field, enter **voicewarmup**.
- 29. Click **OK**. Logging of Windows Installer is now enabled. The log file generated will be in the format msi<random letters and numbers>.log.



- 30. Close the Group Policy window and close the organization unit's Properties window.
- 31. Repeat steps 15 to 36 for other organizational units to select all the users (machines) to which you want to deploy Workshare Professional.

The Workshare package is now ready to be deployed on a per-machine basis. The next time the client machines are rebooted, Workshare will be installed.

Note: Client machines may have to be rebooted more than once depending on their configuration.

Deploying Workshare Desktop


Note: Before installing using this method, please refer to the section, Deploying via the Command Line, page 68.

To deploy Workshare Desktop using Active Directory:

- 1. On the Windows Server machine, create a shared folder with relevant permissions so that client machines can access the Workshare MSI during the automatic installation.
- 2. Extract the Workshare.Desktop.msi file from the EXE install file and copy it into the folder created in step 1.



- Create a transform (MST) file. The transform file is used to specify properties, such as ENABLE_UPDATES, during the installation. The following procedure describes how to create a transform file using the Orca utility provided in the Windows Installer Software Developers Kit.
- 4. Launch Orca.
- 5. Open the Workshare.Desktop.msi file.
- 6. From the *Transform* menu, select **New Transform**. In the title bar of the window, **transformed by Untitled** is displayed in parenthesis the name of the msi.
- 7. In the left pane, select the **Property** table.
- 8. Right-click in the right pane and select **Add Row**.
- 9. Select **Property** in the upper area and enter **ENABLE_UDPATES** in the lower area.
- 10. Select Value in the upper area and enter 0 to disable updates
- 11. Click **OK**.
- 12. Repeat steps 8 to 11 for additional properties as required. You can add any of the properties specified on page 73.
- 13. From the *Transform* menu, select **Generate Transform** and the save the transform file to the shared folder created in step 1.
- 14. From the Start menu, launch **Active Directory Users and Computers**. A list of organizational units is displayed on the left side.




15. You now have to configure a group policy for the users to which you will deploy Workshare Desktop. This is done for each organizational unit that includes users to which you want to deploy.

Workshare

NETWORK DEPLOYMENT


- 16. Right-click an organizational unit and select Properties.
- 17. In the Group Policy tab, click the New button and enter a name for the new policy.
- 18. Select the new policy in the upper area and click the **Properties** button.
- 19. In the **Security** tab, click **Add**. A list of users in the organizational unit is displayed.
- 20. For all users to which you will deploy Workshare Desktop, ensure that at a minimum the following permissions are selected:
 - □ Read
 - Apply Group Policy
- 21. For any users to which you do not want to deploy Workshare Desktop, ensure that the **Apply Group Policy** permission is not selected.
- 22. Click **OK**.
- 23. In the **Group Policy** tab, select the policy in the upper area and click the **Edit** button. The *Group Policy* window is displayed.
- 24. Expand the **Computer Configuration** tree and the **Software Settings** node. The following instructions will install Workshare Desktop per machine.



- 25. Right-click **Software installation** and select **New** then **Package**.
- 26. Browse to the shared folder and select Workshare. Desktop.msi file.
- 27. Click Open. The Deploy Software dialog is displayed.
- 28. Ensure that the **Advanced published or assigned** option is selected and click **OK**.
- 29. In the Modifications tab, click Add.



- 30. Browse to the transform (MST) file created in steps 4 to 13 and click Open.
- 31. Click **OK**.
- 32. In the *Group Policy* window, expand the **Administrative Templates** node and then the **Windows Components** node.
- 33. Select Windows Installer.
- 34. On the right side of the Group Policy window, double-click Logging.
- 35. Select the **Enabled** radio button and in the **Logging** field, enter **voicewarmup**.
- 36. Click **OK**. Logging of Windows Installer is now enabled. The log file generated will be in the format msi<random letters and numbers>.log.



- 37. Close the Group Policy window and close the organization unit's Properties window.
- 38. Repeat steps 15 to 36 for other organizational units to select all the users (machines) to which you want to deploy Workshare Desktop.

The Workshare Desktop package is now ready to be deployed on a per-machine basis. The next time the client machines are rebooted, Workshare Desktop will be installed.

Note: Client machines may have to be rebooted more than once depending on their configuration.



APPENDIX A. ADDITIONAL MSIEXEC.EXE PARAMETERS AND SWITCHES



MSIEXEC.EXE PARAMETERS AND SWITCHES

The executable program that interprets packages and installs products is msiexec.exe. Note that msiexec also sets an error level on return that corresponds to system error codes. The following table describes the parameters and switches for this program. For the latest Msiexec.exe Parameters and Switches, please refer to http://msdn2.microsoft.com/en-us/library/aa367988.aspx.

Switch	Parameters	Meaning
/i	Package ProductCode	Installs or configures a product.
/f	[p o e d c a u m s v] Package ProductCode	Repairs a product. This option ignores any property values entered on the command line. The default argument list for this option is 'pecms'. This option shares the same argument list as the REINSTALLMODE property. p Reinstall only if file is missing. o Reinstall if file is missing or if an older version is installed. e Reinstall if file is missing or an equal or older version is installed. d Reinstall if file is missing or a different version is installed. c Reinstall if file is missing or the stored checksum does not match the calculated value. Only repairs files that have msidbFileAttributesChecksum in the Attributes column of the File table. a Force all files to be reinstalled. u Rewrite all required user specific Registry entries. m Rewrite all required computer-specific Registry entries. s Overwrite all existing shortcuts. v Run from source and re-cache the local package. Do not use the v reinstall option for the first installation of an
		application or feature.
/a	Package	Administrative installation option. Installs a product on the network.
/x	Package ProductCode	Uninstalls a product.



ADDITIONAL MSIEXEC.EXE PARAMETERS AND SWITCHES

Switch	Parameters	Meaning
/j	[u m]Package or [u m]Package /t Transform List or [u m]Package /g LanguageID	Advertises a product. This option ignores any property values entered on the command line. u Advertise to the current user. m Advertise to all users of machine. g Language identification. t Applies transform to advertised package.
/L	[i w e a r u c m o p v + !]Logfile	Specifies path to log file and the flags indicate which information to log. i Status messages w Non-fatal warnings e All error messages a Start up of actions r Action-specific records u User requests c Initial UI parameters m Out-of-memory or fatal exit information o Out-of-disk-space messages p Terminal properties v Verbose output + Append to existing file ! Flush each line to the log "*" Wildcard, log all information except for the v option. To include the v option, specify "/I*v".



ADDITIONAL MSIEXEC.EXE PARAMETERS AND SWITCHES

Switch	Parameters	Meaning
/m	filename	Generates an SMS status .mif file. Must be used with the install (-i), remove (-x), administrative installation (-a), or reinstall (-f) options. The ISMIF32.DLL is installed as part of the SMS and must be on the path.
		The fields of the status mif file are filled with the following information:
		Manufacturer - Author
		Product - Revision Number
		Version - Subject
		Locale - Template
		Serial Number - not set
		Installation - set by ISMIF32.DLL to "DateTime"
		InstallStatus - "Success" or "Failed"
		Description - Error messages in the following order: 1) Error messages generated by installer. 2) Resource from Msi.dll if install could not commence or user exit. 3) System error message file. 4) Formatted message: "Installer error %i", where %i is error returned from Msi.dll
/p	PatchPackage	Applies a patch. To apply a patch to an installed administrative image you must combine options as follows:
		/p <patchpackage> /a <package></package></patchpackage>
/q	n b r f	Sets user interface level.
		q No UI
		qn No UI
		qb Basic UI. Use qb! to hide the Cancel button.
		qr Reduced UI with no modal dialog displayed at the end of the installation.
		qf Full UI and any authored FatalError, UserExit, or Exit modal dialoges at the end.
		qn+ No UI except for a modal dialog displayed at the end.
		qb+ Basic UI with a modal dialog displayed at the end. The modal box is not displayed if the user cancels the installation. Use qb+! or qb!+ to hide the Cancel button.
		qb- Basic UI with no modal dialoges. Please note that /qb+- is not a supported UI level. Use qb-! or qb!- to hide the Cancel button.
		Note that the ! option is available with Windows Installer version 2.0 and works only with basic UI. It is not valid with full UI.



ADDITIONAL MSIEXEC.EXE PARAMETERS AND SWITCHES

Switch	Parameters	Meaning
/? or /h		Displays copyright information for the Windows Installer.
/у	Module	Calls the system API DllRegisterServer to self-register modules passed in on the command line. For example, msiexec /y my_file.dll. This option is only used for Registry information that cannot be added using the Registry tables of the MSI file.
/z	Module	Calls the system API DllUnRegisterServer to unregister modules passed in on the command line. For example, msiexec /z my_file.dll. This option is only used for Registry information that
		cannot be removed using the Registry tables of the MSI file.

The options /i, /x, /f[p|o|e|d|c|a|u|m|s|v], /j[u|m], /a, /p, /y and /z should not be used together. The one exception to this rule is that patching an administrative installation requires using both /p and /a. The options /t and /g should only be used with /j. The options /l and /q can be used with /i, /x, /f[p|o|e|d|c|a|u|m|s|v], /j[u|m], /a, and /p.



APPENDIX B. DEFAULT PROFILE



WORKSHARE DEFAULT PROFILE

A profile is a collection of policies that include a set of instructions to Workshare Protect as to what metadata to remove from an email attachment and whether to convert the attachment to PDF.

Workshare Protect uses a default profile called **WorkshareClient.policy** at the following location: ProgramData/Workshare/PolicySets/ClientProfiles/Default/. The same profile can also be found in a user's local folder as follows: Users/[current user]/Documents/My Policies. When a new user logs in, the default profile is copied to their My Policies folder.

Additionally, a copy of this profile is created in a file called **WorkshareClient.runtimepolicy** at the following location: ProgramData/Workshare/PolicySets/ClientProfiles/Default/. It is actually the runtimepolicy file that Workshare Protect applies as the profile.

A user can change the profile by modifying the parameters in the Workshare Configuration Manager. Any changes made there update the following files: **WorkshareClient.runtimepolicy** (in the user's My Policies folder) and **WorkshareClient.runtimepolicy**.

The default profile includes the following policies:

Document Conversion Policy

This policy converts Microsoft Office files to PDF when they are emailed.

This policy includes the following expression:

• File type is Word, Excel, PowerPoint or RTF.

The actions to apply when the condition is met are as follows:

• Email Channel Action: Everyone to Internal: PDF; Everyone to External: PDF (meaning the document is converted to PDF when emailed to an external or an internal recipient)

Hidden Data Policy

This policy prevents the unauthorized disclosure of hidden data such as track changes, speaker notes and hidden columns. Depending on the type of hidden data and user privilege, the data is either automatically removed or the user is given the choice to clean the data or disregard the alert.

This policy includes the following expressions:

- Any document (Microsoft Word, Excel or PowerPoint, or RTF) contains high risk hidden data (comment, track change item, hidden text, small text, white text, version, auto version, link, speaker notes, hidden slides), or
- Any document contains medium risk hidden data (reviewer, hyperlink, routing slip, variable, macro, custom property, ink annotations), or
- Any document contains low risk hidden data (attached template, field, built-in property, document statistic, smart tag)

Workshare D

DEFAULT PROFILE

The action to apply when the condition is met is as follows:

 Email Channel Action: Everyone to External: Clean Hidden Data (meaning when the document is emailed to an external recipient, the hidden data is removed from the document)

Hidden PDF Data Policy

This policy prevents the unauthorized disclosure of hidden data such as markups, properties, attachments and bookmarks.

This policy includes the following expression:

• Any PDF document contains markups, properties, attachments and bookmarks.

The action to apply when the condition is met is as follows:

• Email Channel Action: Everyone to Internal: Clean hidden data; Everyone to External: Clean hidden data (meaning when the document is emailed to an external recipient, the hidden data is removed from the document)

Full Document Restriction Policy

This policy prevents documents that have the Workshare classification "full document restriction" from being emailed.

This policy includes the following expressions:

- Any file type has a Workshare 'Full Restriction' status.
- Custom property 'WSClassification' is 'Full Restriction'

The action to apply when the condition is met is as follows:

• Email Channel Action: Everyone to Internal: Block; Everyone to External: Block (meaning the document cannot be emailed to an external or an internal recipient)

External Document Restriction Policy

This policy prevents documents that have the Workshare classification "external document restriction" from being emailed externally.

This policy includes the following expressions:

- Any file type has a Workshare 'External Only Restriction' status.
- Custom property 'WSClassification' is 'External Only Restriction'

The actios to apply when the condition is met is as follows:

• Email Channel Action: Everyone to External: Block (meaning the document cannot be emailed to an external recipient)



For Internal Use Only Policy

This policy prevents documents that have the Workshare classification "for internal use only" from being emailed externally.

This policy includes the following expression:

• Custom property 'WSClassification' is 'For Internal Use Only'

The actions to apply when the condition is met are as follows:

• Email Channel Action: Everyone to External: Block (meaning the document cannot be emailed to an external recipient)

Confidential Policy

This policy alerts users when documents that have the Workshare classification "confidential" are emailed the Workshare Protect *Email Security* dialog is used. This policy does not alert for the *Protect Profile* dialog.

This policy includes the following expression:

· Custom property 'WSClassification' is 'Confidential'

The action to apply when the condition is met is as follows:

• Email Channel Action: Everyone to Internal: Alert; Everyone to External: Alert (meaning when the document is emailed to an external or an internal recipient, the user is alerted)

Highly Confidential Policy

This policy prevents documents that have the Workshare classification "highly confidential" from being emailed.

This policy includes the following expression:

· Custom property 'WSClassification' is 'Highly Confidential'

The action to apply when the condition is met is as follows:

• Email Channel Action: Everyone to Internal: Block; Everyone to External: Block (meaning the document cannot be emailed to an external or an internal recipient)



APPENDIX C.WORKSHARE PREREQUISITES



WORKSHARE PREREQUISITES

Summary

The prerequisites for Workshare Professional/Compare/Protect 9 depend on the version of the operating system and the version of Microsoft Office. They are listed on page 12 and further details provided in this appendix. Prerequisites for other versions of Workshare Professional/Compare/Protect may be slightly different.

Microsoft .NET Framework 4.5

The full version of Microsoft .NET Framework 4.5 (no service pack) is required.

The executable file can be downloaded by clicking this link:

http://download.microsoft.com/download/b/a/4/ba4a7e71-2906-4b2d-a0e1-80cf16844f5f/dotnetfx45_full_x86_x64.exe

Microsoft Visual C++ 2012 Redistributable Package (x86)

Microsoft Visual C++ 2012 Redistributable Package (x86) is required.

The executable file can be downloaded by following this link:

http://www.microsoft.com/en-gb/download/details.aspx?id=30679

Microsoft Visual C++ 2012 Redistributable Package (x64)

Microsoft Visual C++ 2012 SP1 Redistributable Package (x64) is required for the native x64 code in the application.

The executable file can be downloaded by following this link:

http://www.microsoft.com/en-gb/download/details.aspx?id=30679

Microsoft Visual Studio 2010 Tools for Office Runtime Setup

Required to run Microsoft Office based solutions built using Microsoft Visual Studio 2010 and 2012.

The executable file can be downloaded by clicking this link:

http://download.microsoft.com/download/9/4/9/949B0B7C-6385-4664-8EA8-3F6038172322/vstor redist.exe